

PICC Line Care²¹



- Avoid venipuncture, peripheral intravenous cannula insertion, and taking blood pressure on the same arm where the PICC is located. Place reminder signs for the health care team members according to agency policy.
- Ensure the PICC line dressing stays dry during showering.
- Avoid bandages or tight coverings over the PICC line insertion point. Tight elastic coverings can increase the risk of compressing the vein, leading to vein wall irritation, phlebitis, or thrombosis.

21. Cancer Institute NSW. (2021, July 19). *Central venous access devices*. <https://www.eviq.org.au/clinical-resources/central-venous-access-devices-cvads/112-central-venous-access-devices#key-practice-points-for-clinical-procedures>

4.3 Applying the Nursing Process

Ongoing nursing assessments and interventions are essential to provide safe, quality care when a client has a CVAD. These actions are guided by evidence-based practice standards. In acute care and outpatient settings, the overall goals of CVAD infusion therapy are safe administration of medications and the absence of complications.

Nurses provide routine care and maintenance of CVADs after their insertion, including the following responsibilities:

- Providing for ongoing assessment of the insertion site and the infusion system to ensure it is functioning as expected
- Performing CVAD dressing changes while ensuring catheter stabilization
- Accessing CVADs
- Performing intravenous line care and management
- Flushing and locking CVADs
- De-accessing inserted and implanted CVADs
- Performing blood sampling from a CVAD

The nurse may also be involved in other activities related to safe use of CVADs such as culturing for suspected infections and advocating for catheter removal as soon as it is no longer indicated for treatment. In home care and outpatient settings, the nurse also provides education to the client and their family members on how to safely manage the CVAD and when to call the provider with concerns.

Assessment

The nurse must be knowledgeable about the different types and placement locations of CVADs as described in Table 4.2a in the “[Basic Concepts](#)” section. Regardless of which type of CVAD device is used, the nurse must routinely assess the site and dressing for integrity, signs of infection, catheter migration, and other signs of complications. Areas beyond the site of insertion must also be assessed, such as the adjacent skin, neck, chest area, and the extremity on the side where the central line is placed. If the catheter is

tunneled under the skin, assessment also includes monitoring for pain, swelling, drainage, or erythema. External length is measured at the time of insertion and used for future measurement comparison. If a PICC line is in place, arm circumference is also measured each shift and results compared to previous readings. If arm circumference consistently increases, a deep vein thrombosis may be suspected.

The frequency of site assessment is dependent on the client's condition and agency policies. Typically, in the acute care setting, site assessment is performed every shift. If the client is in the home care setting, they are educated on how to inspect their site and how frequently this assessment should occur. Home health nurses will assess the site and arm circumference during each visit.

Accurate documentation of site assessment and related monitoring are essential. Documentation of the assessment in the client's medical record should include CVAD location, type of dressing, site assessment specifics, presence of any complications, and any actions or interventions performed. Table 4.3a summarizes the assessments related to CVADs.

Table 4.3a Summary of CVAD Assessments

Assessment* *Assessment of the CVAD should occur at least once every shift and as needed in acute care settings.	Description
Assess the entire infusion system.	A complete assessment includes the insertion site and surrounding area, securement device, functioning of the CVAD, and tip location.
Assess for proper functioning of the device.	Observe for constant flow of fluids, high pressure, or occlusion alarms. Assess for blood flow.
Inspect the CVAD dressing.	Determine if the dressing is clean, intact, and dated.
Inspect and palpate the insertion site and surrounding area through the intact dressing.	Check for redness, bluish discoloration on darker skin, swelling, drainage, or a palpable cord. Ask the client if they are experiencing any pain, paresthesia, numbness, or tingling around the area.
Measure the external catheter length.	Compare the measurement results to the initial placement verification results to detect any catheter migration or dislodgement.
Measure the upper arm circumference for PICC lines.	Monitor circumference measurements each shift and compare results. Increasing measurements may indicate possible edema and deep vein thrombosis (DVT). Measurement of the arm circumference should occur 10 cm above the antecubital fossa and compared to the baseline measurement. A 3 cm increase in the circumference may indicate edema associated with a DVT.
Ensure correct labeling of all infusing fluids.	Follow agency policy and procedures for labeling infusing IV fluid and medications.
Ensure all Luer-lock connections are secure.	Secure connections provide safety in guarding against microorganism and air entrance into the closed system, as well as leakage of medications out of the system.

Document the complete assessment in the client EMR.

Complete assessment documentation helps support QSEN or other quality and safety standard informatics.

CVAD Dressing Changes and Site Care

CVAD dressing changes should occur routinely at established intervals according to evidence-based guidelines and agency policies. Many agencies have designated CVAD dressing kits. The dressing protects the insertion site and surrounding tissue from microorganism growth that can accumulate within CVAD hubs and the skin and cause a CLABSI.¹ Ensuring a clean, dry, and intact dressing helps prevent microorganisms from entering the bloodstream.

If the integrity of the CVAD dressing is compromised by moisture or drainage, becomes loose, or if signs of infection are apparent, the dressing should be replaced immediately. The dressing should be labeled with the date, time, and initials of the person completing the task. All CVAD dressing changes should be documented in the client's medical record per agency policy.

CVAD site care is routinely performed, typically at the same time as the dressing change. Aseptic technique is required when providing site care and dressing changes with meticulous hand hygiene, sterile gloves, and a mask. The preferred skin disinfectant is 2% chlorhexidine for a client older than two months of age.² Chlorhexidine skin disinfectant provides antibacterial activity that persists for several hours after it is applied.

Implanted ports require dressings until the area is healed after the port has been implanted under the skin, as well as when accessing the port for intermittent and/or continuous infusions. A specialized noncoring needle is used when accessing implanted ports. (Refer to specific information on

1. NSW Agency for Clinical Innovation. (2021). *Central venous access devices (CVAD): Clinical practice guide*. Agency for Clinical Innovation. https://aci.health.nsw.gov.au/_data/assets/pdf_file/0010/239626/ACI-CVAD-clinical-practice-guide.pdf

2. Centers for Disease Control and Prevention. (2015, November 5). *Summary of recommendations: Guidelines for the prevention of intravascular catheter-related infections (2011)*. <https://www.cdc.gov/infectioncontrol/guidelines/bsi/recommendations.html>

“Accessing and De-accessing an Implanted Venous Access Device” later in this section.)

The dressing regimen for tunneled catheters within the acute care setting is typically the same as for nontunneled catheters. However, if the tunneled area is well-healed, a dressing may not be required in the outpatient setting.

There are different types of dressings that may be selected for a CVAD dressing change based on client status, agency policy, and evidence-based guidelines. Transparent semipermeable membrane (TSM) or simple gauze dressings are commonly used. Because TSM dressings are transparent, they allow visualization and inspection of the site area without removing or disturbing the dressing. They are also cost-effective and promote a closed system. Gauze dressings are commonly used for clients who perspire excessively, which interferes with a TSM dressing staying in place. A gauze dressing is also appropriate if the site is draining or if the person has a sensitivity to the transparent dressing.

Per CDC guidelines and infusion nursing’s standards of practice, TSM dressings should be changed at a minimum of every seven days, whereas gauze dressings must be changed at least every 48 hours. Dressings must also be changed as needed, such as for loss of dressing integrity, the presence of drainage or moisture, or signs of infection.³

TSM dressings with an impregnated chlorhexidine gel or disc are a newer technology that are becoming more commonly used. An antiseptic foam disc is placed around the catheter insertion site and covered with a TSM dressing. Other TSM dressings have an impregnated chlorhexidine gel within the dressing that is placed over the catheter insertion site. The CDC has not yet made a recommendation regarding use of impregnated dressings.⁴ See Figure 4.8⁵ for an image of a quad lumen CVAD with an impregnated

3. Gorski, L. (2021). A look at 2021 infusion therapy standards of practice. *Home Healthcare Now*, 39(2), 62-71.

https://www.nursingcenter.com/wkhlrp/Handlers/articleContent.pdf?key=pdf_01845097-202103000-00002

4. Centers for Disease Control and Prevention. (2015, November 5). *Summary of recommendations: Guidelines for the prevention of intravascular catheter-related infections (2011)*. <https://www.cdc.gov/infectioncontrol/guidelines/bsi/recommendations.html>

5. “ID-112-CVAD-IJ-CICC-Oct-2020-2.jpeg” by E. Alexandrou used with permission. Access the original image at <https://www.eviq.org.au/clinical-resources/central-venous-access-devices-cvads/112-central-venous-access-devices#short-term-cvads>

chlorhexidine disc, subcutaneous and adhesive external securement device (ESD), and bordered semipermeable dressing. In practice, all access ports would have sterile caps attached according to evidence-based practices for infection control.



Figure 4.8 Quad lumen CVAD with a Chlorhexidine (CHG) Disc, Subcutaneous and Adhesive External Securement Device (ESD), and Bordered Semipermeable Dressing

Before performing a CVAD dressing change, review the client's medical record for previous history, allergies (including allergies to tape or adhesives), previous or baseline length and circumference measurements, and the type of dressing used. Most acute care settings utilize a central line dressing kit that includes standardized accessories necessary for the procedure.

When performing CVAD dressing changes, using aseptic nontouch technique (ANTT) is considered a global standard. The "**ANTT approach**" identifies key parts and key sites throughout the preparation and implementation of the procedure. A **key part** is any sterile part of equipment used during an aseptic procedure, such as needle hubs and dressings. A **key**

site is the insertion site, nonintact skin, or an access site for medical devices connected to clients. CVAD insertion sites are considered key sites. ANTT includes four underlying principles to keep in mind while performing invasive procedures:

- Always perform meticulous hand hygiene.
- Never contaminate key parts.
- Touch nonkey parts with confidence.
- Take appropriate infection control precautions.

Review Table 4.3b for a summary of CVAD dressing change steps and their rationale.

Table 4.3b CVAD Dressing Change Steps

Step

Follow standard aseptic nontouch technique (ANTT). Standard ANTT requires the use of a general aseptic field, such as a single use or disinfected surface for placement of all needed supplies to provide a controlled workspace and to promote asepsis. Apply PPE according to the client's health conditions. The client and the RN both wear a mask during a dressing change to prevent contamination of the site area. Ask the client to turn their head in the opposite direction of the dressing change site to avoid potential contamination of the site.

- Standard ANTT and PPE reduce the risk of microorganism contamination and exposure to body fluids.

Nonsterile gloves are acceptable when removing a CVAD dressing. When removing the dressing, carefully roll up the edges and remove toward the insertion of the catheter to prevent dislodgement. After removing the dressing, remove the nonsterile gloves, perform hand hygiene, and don sterile gloves.

Most securement devices are integrated within the CVAD dressing kit and are changed with the dressing. If the catheter is secured with sutures, gently and carefully lift the suture plate to cleanse with agency-approved antiseptic, maintaining aseptic technique.

Cleanse the insertion site and surrounding skin with each dressing change using aseptic technique. Using chlorhexidine solution is considered standard practice, but if the client has an allergy or hypersensitivity to its use, povidone-iodine may be used as an alternative. A single-use antiseptic applicator is commonly used. When cleansing, do so in a back-and-forth motion for 30 seconds and allow it to dry. If dry blood or drainage is present on the skin and around the insertion site, it should be cleansed and removed using sterile technique prior to applying a new dressing.

Label the dressing with the date, time, and your initials, as well as the date the dressing should be changed again.

- Labeling is a quality measure to promote ongoing adherence to agency policies and recommendations.

Document the related assessments, cleansing, and dressing change in the client's medical record.

- Documentation in the legal record is required and is also used for reimbursement and quality improvement initiatives.

Accessing CVADs

Each time a CVAD is accessed, there is a chance for exposure to microorganisms from the clinician, the environment, or the client. To reduce this exposure, accessing and manipulations of a CVAD should be kept at a minimum. Adhering to strict hand hygiene and ANTT standards are important strategies to reduce the risk of infection.

When accessing a CVAD, the CVAD access hub or needleless port must be decontaminated with a vigorous scrub technique with a single-use aseptic swab or a scrub hub. A **scrub hub** is a specific scrubbing device for CVAD hubs and embedded with chlorhexidine and alcohol or 70% alcohol to disinfect catheter hubs or needleless connectors. The suggested scrub time is up to 60 seconds with a minimum of 15 seconds. When decontaminating the hub, generate friction by scrubbing in a twisting motion like juicing an orange. Ensure the top of the hub is scrubbed, as well as the sides.⁶

An alternative to aseptic swabs or scrub hubs is **aseptic-impregnated catheter hub** protective caps. These caps contain a sponge that is saturated with alcohol or chlorhexidine. They are attached to the access ports and eliminate the need to perform the vigorous scrub. After the caps are removed, they are discarded, and a new sterile cap is applied.

Flushing and Locking CVADs

Flushing is a manual injection of 0.9% sodium chloride to clean the lumen of the catheter. **Locking** is the injection of a limited volume of a liquid following the catheter flush, for the period of time when the catheter is not used, to prevent intraluminal clot formation and/or catheter colonization.⁷

CVADs require flushing to maintain patency of the line(s) and to prevent the mixing of incompatible solutions and/or medications. The recommended

6. The Joint Commission. (2023). *Central line-associated bloodstream infection toolkit and monograph*. <https://www.jointcommission.org/resources/patient-safety-topics/infection-prevention-and-control/central-line-associated-bloodstream-infections-toolkit-and-monograph/>

7. Godelieve, A. G. (2015). Flushing and locking of venous catheters: Available evidence and evidence deficit. *Nursing Research and Practice*, 2015. <https://doi.org/10.1155/2015/985686>

flush is sterile 0.9% sodium chloride unless manufacturer or agency policy requires flushing with an alternate solution.

Central line catheters are flushed according to agency policy. They must be flushed immediately after placement of the initial insertion has been verified, before and after each fluid or medication infusion, and before and after drawing blood from the central line. Additionally, flushing of all lumens of a multi-lumen catheter should be considered after obtaining blood samples to reduce the possibility of blood influx into other lumens due to changing intraluminal pressure. If a CVAD is not being routinely accessed, it is typically flushed and locked every seven days. Implantable ports that are not being accessed should be flushed and locked every 4-6 weeks.⁸

A 10-mL or larger syringe is used to access a CVAD to prevent excess pressure that can damage the lumen. Before flushing the lumen with 0.9% sodium chloride, aspiration of blood should be attempted to ensure patency. The volume of fluid used for flushing should be twice the volume of the lumen.

Instilling the flush fluid into the catheter lumen allows a column of fluid to maintain its patency. A pulsatile flushing technique is recommended with ten small boluses of 1 mL of fluid interrupted by brief pauses. This technique has been found to be more effective at removing solid deposits (such as fibrin, drug participate, or intraluminal bacteria) compared to continuous low flow techniques.⁹ Flushing should never occur if force is required against resistance because this can cause rupture of the catheter or mobilization of an occlusive clot.

If resistance is met while flushing or there is inadequate blood return on aspiration, troubleshoot for potential causes and solutions such as repositioning or removing kinks in lines. If these initial steps are not successful, follow agency policy in using a thrombolytic medication (i.e.,

8. Gorski, L. A., Hadaway, L., Hagle, M. E., Broadhurst, D., Clare, S., Kleidon, T., Meyer, B. M., Nickel, B., Rowley, S., Sharpe, E., & Alexander, M. (2021). Infusion therapy standards of practice (8th ed.). *Journal of Infusion Nursing: The Official Publication of the Infusion Nurses Society*, 44(1S Suppl 1), S1–S224. <https://doi.org/10.1097/NAN.0000000000000396>

9. Gorski, L. A., Hadaway, L., Hagle, M. E., Broadhurst, D., Clare, S., Kleidon, T., Meyer, B. M., Nickel, B., Rowley, S., Sharpe, E., & Alexander, M. (2021). Infusion therapy standards of practice (8th ed.). *Journal of Infusion Nursing: The Official Publication of the Infusion Nurses Society*, 44(1S Suppl 1), S1–S224. <https://doi.org/10.1097/NAN.0000000000000396>

alteplase) or requesting an order for a port study or central line study with fluoroscopy.

There are different types of needleless connectors through which the CVAD is flushed. If using a negative needleless connector, clamp the lumen while injecting the last 0.5 mL and before the syringe is disconnected to prevent blood reflux back into the catheter tip when the syringe is disconnected. If using a positive needleless connector, clamp after the syringe is disconnected to allow the internal mechanism to activate. For neutral (anti-reflux) needleless connectors, there is no specific clamping procedure required.

Instilling a “locking” fluid into a CVAD catheter causes a column of fluid within the catheter to maintain patency. Recommendations regarding the type of locking solution to use vary. Some studies suggest 0.9% normal saline is as effective as heparin. Follow agency policy and recommendations from the manufacturer.¹⁰

Standard ANTT (Aseptic Nontouch Technique) is used when flushing and locking central lines, as well as when infusing other fluids and medications. ANTT requires use of meticulous hand hygiene and a single use or disinfected surface for placement of all supplies to provide a controlled workspace and promote asepsis.¹¹

Accessing and De-Accessing an Implanted Venous Access Device

The management and care of an implanted venous access device (IVAD), as recommended by the CDC, includes utilizing proper aseptic technique before palpating, accessing, or performing dressing changes. See Figure 4.9¹² for an image of an IVAD that has been placed.

10. Gorski, L. (2021). A look at 2021 infusion therapy standards of practice. *Home Healthcare Now*, 39(2), 62-71. https://www.nursingcenter.com/wkhlrp/Handlers/articleContent.pdf?key=pdf_01845097-202103000-00002

11. Gorski, L. (2021). A look at 2021 infusion therapy standards of practice. *Home Healthcare Now*, 39(2), 62-71. https://www.nursingcenter.com/wkhlrp/Handlers/articleContent.pdf?key=pdf_01845097-202103000-00002

12. “Port-catheter.jpg” by Una Smith (talk) is licensed under [CC0](https://creativecommons.org/licenses/by/4.0/)



Figure 4.9 Implanted Venous Access Device (IVAD)

When accessing an IVAD, the skin at the site of access must be disinfected with chlorhexidine solution and allowed to dry before accessing the device. Many clients require a lidocaine medication (i.e., EMLA cream or intradermal lidocaine injection) prior to port access to prevent pain. This is especially true for vulnerable populations requiring IVADs such as pediatric, elderly, and oncology clients.

A noncoring needle must be used for accessing IVADs to prevent damage to the device. See Figure 4.10¹³ for images related to accessing an IVAD.

13. "[Diagram showing an implantable port under the skin CRUK_100.svg](#)" by Cancer Research UK and "[Venous Access Port Catheter.png](#)" by BruceBlaus are both licensed under [CC BY-SA 4.0](#)




Figure 4.10 Implanted Venous Access Device

Some IVADs are “power-injectable” while others are not. This means that some ports can tolerate the pressure required for CT injectable dye while others cannot. The type of needle used to access the port depends on what type of port the client has implanted. Clients with a power-injectable port should have an ID card, bracelet, and some type of identifier. This information should also be recorded in the medical record. If no information is available, the port should be treated as a nonpower injectable port and accessed with a normal port needle and not used for CT dye.

As with all long-term vascular access devices, IVADs are at risk for occlusion or loss of patency because protein buildup can occur on the surface of the device. Flushing and locking implanted ports help to prevent occlusion, but there are no clear recommendations for standardized flushing techniques or volumes. Recommendations from the manufacturers vary with the type of device regarding the use of heparin or saline. Flushing guidelines are typically established by the manufacturer and agency policy.¹⁴ Currently, the consensus of recommendations for flushing implanted ports that are used a minimum of every 8 hours in adult clients is to flush after each infusion of medication or blood administration with 10 mL of 0.9% normal saline or every 24 hours according to the manufacturer’s recommendations.

14. Blanco-Guzman, M. O. (2018). Implanted vascular access device options: A focused review on safety and outcomes [Review]. *Transfusion*, 58, 558-568. <https://onlinelibrary.wiley.com/doi/pdfdirect/10.1111/trf.14503>

The majority of techniques that are used for locking IVADs consist of withdrawing the syringe while still applying positive pressure during the injection of the last 0.5 mL of fluid volume. The volume used for locking depends on the reservoir volume and catheter diameters. Formal recommendations for maintenance locking in implanted ports are to flush with 10 mL 0.9% normal saline every four weeks in closed ports. For open-implanted ports, the recommendation is to flush with 10 mL normal saline followed by 5 mL heparin every four weeks.¹⁵ The dose of heparin required to maintain patency can vary from 10 to 1,000 IU/mL, with the concentration of 100 IU/mL in a volume of 3 mL the most commonly used.¹⁶

Current recommendations for the maintenance of implanted ports indicate the needle should be changed and the port re-accessed every seven days.¹⁷



View a supplementary YouTube video¹⁸ on CVAD access and care: [Ports: Access and Care.](#)

Blood Sampling From a CVAD

Obtaining a blood sample from a CVAD is a responsibility of the registered nurse. Multiple venipunctures frequently occur in acute care settings due to the severity of the medical condition in a client who requires a CVAD. The main advantage of using a CVAD for frequent blood sampling is decreased pain and anxiety compared to the experience of multiple peripheral venipunctures. However, accessing CVADs also has potential risks associated

15. Blanco-Guzman, M. O. (2018). Implanted vascular access device options: A focused review on safety and outcomes [Review]. *Transfusion*, 58, 558-568. <https://onlinelibrary.wiley.com/doi/pdfdirect/10.1111/trf.14503>

16. Oliveira, F. J. G., Rodrigues, A. B., Ramos, I. C., & Caetano, J. Á. (2020). Dosage of heparin for patency of the totally implanted central venous catheter in cancer patients. *Revista Latino-Americana de Enfermagem*, 28, e3304. <https://doi.org/10.1590/1518-8345.3326.3304>

17. Oncology Nursing Society. (2017). *Access device standards of practice for oncology nursing*. <https://www.ons.org/books/access-device-standards-practice-oncology-nursing>

18. Moffott Cancer Center. (2018, October 31). *Ports: Access and care* [Video]. YouTube. All rights reserved. <https://youtu.be/KtCwEdQbPRQ>

with infection, occlusion, and improper sample taking, resulting in inaccurate test results. Following evidence-based infection prevention practices, limiting the frequency of blood sampling, and following ANTT guidelines help reduce the risk of infection. A summary of key points related to blood sampling from CVADs is outlined in Table 4.3d. See the “[Checklist: Obtain a Blood Sample From a CVAD](#)” for the complete steps for this procedure. Note that current guidelines recommend to not use CVADs infusing parental nutrition for blood sampling because manipulation may increase the risk for CLABSI.¹⁹



During the blood sampling procedure, if any signs or symptoms occur indicating an air embolism, place the client on the left side in Trendelenburg or left lateral decubitus position, call the rapid response team, and notify the provider.

Table 4.3d Summary of Key Points Related to Blood Sampling From a CVAD

19. Gorski, L. (2021). A look at 2021 infusion therapy standards of practice. *Home Healthcare Now*, 39(2), 62-71.
https://www.nursingcenter.com/wkhlrp/Handlers/articleContent.pdf?key=pdf_01845097-202103000-00002

Steps	Rationale
<p>Stop the infusion of fluids and medications into the catheter's lumens.</p>	<p>Stopping the infusion of fluids or medications prevents these substances from interfering with the blood sample. Current guidelines do not specify a standard length of time for stopping the infusion, but it is associated with the internal volume of the specific CVAD.²⁰</p>
<p>Choose the appropriate CVAD lumen for obtaining samples based on the largest lumen or the configuration of the lumen exit sites.</p>	<p>Blood draw requires a large lumen. For catheters with a staggered lumen exit at the tip, the sample should be drawn from the lumen exiting at the point farthest away from the heart and above other lumen exits used for infusion.²¹ Follow CVAD manufacturer's instructions for these decisions.</p>
<p>Vigorously scrub the needless connector for at least 15 seconds with antiseptic scrub and let it dry completely.²²</p>	<p>Scrubbing prevents microorganism contamination, and drying prevents contamination by substances.</p>
<p>Attach a prefilled 10-mL syringe of preservative-free normal saline to the needless connector using ANTT. Unclamp the catheter and thoroughly flush the lumen with 10-20 mL of preservative-free 0.9% normal saline.²³ Aspirate slowly for blood, noting the characteristics of the whole blood.</p>	<p>A 10-mL syringe generates lower pressure within the catheter and prevents lumen rupture and/or occlusion.</p>
<p>Clear the dead space by using the push-pull method or discarding the aspirated blood according to agency policy. The discard method requires initial aspiration of 2 to 25 mL of blood (per internal volume of the CVAD, saline flushing prior to drawing the discard volume, and specific laboratory tests needed) and then discarding the syringe before performing the blood sampling.²⁴ The push-pull method utilizes the same syringe used when aspirating to test patency of the catheter. With the syringe still attached, 4 mL to 6 mL of blood is aspirated and then pushed back into the catheter. This aspiration and reinfusion sequence is repeated for four cycles. The blood and syringe are then discarded.²⁵</p>	<p>Either method clears the CVAD catheter's dead space volume and removes any of the blood that becomes diluted with the flush solution. Performing the push-pull method for four cycles allows for an accurate blood sample and also reduces phlebotomy-associated blood loss, particularly when obtaining multiple blood samples. For the discard method, coagulation studies require the largest discard volume to produce accurate results, but this volume of discarded blood can lead to hospital-acquired anemia.</p>

After obtaining the blood sample, thoroughly flush the CVAD lumen with 10-20 mL of preservative-free 0.9% normal saline.²⁶

Flushing thoroughly prevents occlusion.

Evaluation

Daily evaluation for the necessity of continuing the CVAD is important and supported by the CLABSI prevention guidelines. Evaluating the client's cardio-respiratory status every shift and as needed per client condition prompts early recognition of potential complications.

Clients who are receiving infusion therapy and/or medication treatment require ongoing monitoring of laboratory values, intake/output, daily weights, and vital signs to evaluate their current fluid and electrolyte balances.

Nurses also evaluate the client's understanding of the CVAD. If the client will be discharged home with an IVAD, it is imperative they understand how to manage their device safely and when to notify the provider. They will also need referrals to a home health agency, as well as supplies to manage the device on an outpatient basis, such as extra dressings, flushes, and tubing.

20. Gorski, L. (2021). A look at 2021 infusion therapy standards of practice. *Home Healthcare Now*, 39(2), 62-71. https://www.nursingcenter.com/wkhlrp/Handlers/articleContent.pdf?key=pdf_01845097-202103000-00002
21. Gorski, L. (2021). A look at 2021 infusion therapy standards of practice. *Home Healthcare Now*, 39(2), 62-71. https://www.nursingcenter.com/wkhlrp/Handlers/articleContent.pdf?key=pdf_01845097-202103000-00002
22. The Joint Commission. (2023). *Central line-associated bloodstream infection toolkit and monograph*. <https://www.jointcommission.org/resources/patient-safety-topics/infection-prevention-and-control/central-line-associated-bloodstream-infections-toolkit-and-monograph/>
23. Gorski, L. (2021). A look at 2021 infusion therapy standards of practice. *Home Healthcare Now*, 39(2), 62-71. https://www.nursingcenter.com/wkhlrp/Handlers/articleContent.pdf?key=pdf_01845097-202103000-00002
24. Gorski, L. (2021). A look at 2021 infusion therapy standards of practice. *Home Healthcare Now*, 39(2), 62-71. https://www.nursingcenter.com/wkhlrp/Handlers/articleContent.pdf?key=pdf_01845097-202103000-00002
25. McBride, C., Miller-Hoover, S., & Proudfoot, J. A. (2018). A standard push-pull protocol for waste-free sampling in the pediatric intensive care unit. *Journal of Infusion Nursing: The Official Publication of the Infusion Nurses Society*, 41(3), 189-197. <https://doi.org/10.1097/NAN.0000000000000279>
26. Gorski, L. (2021). A look at 2021 infusion therapy standards of practice. *Home Healthcare Now*, 39(2), 62-71. https://www.nursingcenter.com/wkhlrp/Handlers/articleContent.pdf?key=pdf_01845097-202103000-00002

4.4 Checklist: Change a CVAD Dressing and Needleless Connector

**Disclaimer: Always follow agency policy and manufacturer recommendations*

Checklist: Change a CVAD Dressing and Needleless Connector^{1,2}

- Review the client's medical record for information related to the central venous access device and indications.
- Determine the date of the last dressing change.
- Gather the necessary equipment:
 - Antiseptic (chlorhexidine preferred)
 - Sterile transparent semipermeable dressing (may be chlorhexidine-impregnated) or sterile 4" × 4" (10-cm × 10-cm) gauze pad
 - Sterile tape
 - Sterile drape
 - Alcohol-free skin barrier solution
 - Sterile gloves
 - Gloves
 - Masks x 2 (one for nurse and one for the client)
 - Label
 - Sterile needless connectors
 - Sterile disinfectant caps
 - Sterile, preservative-free, prefilled syringes with 10 mL 0.9% normal saline (Number of syringes required based on number of lumens of the CVAD)
 - Stabilization device, if indicated, such as a Stat Lock or Stay Fix
 - Antimicrobial patch or biopatch for placement over the insertion site
 - *Many facilities have sterile pre-packaged CVAD dressing kits that contain the necessary supplies for a CVAD dressing change. Use of pre-packaged kits is recommended when available.

1. *Clinical skills: Essentials collection* (1st ed.). (2021). Elsevier.

2. Lippincott procedures. <http://procedures.lww.com>

- Perform hand hygiene.
- Confirm the client's identity using at least two patient identifiers and check allergies.
- Provide privacy.
- Explain the procedure to the client and family (if appropriate) and answer any questions. Family members should also wear a mask if present in the room during the dressing change.
- Raise the bed to the appropriate working height.
- Measure the external catheter length through the intact dressing.
- Put on a mask. Instruct the client to put on a mask and turn their head opposite from the CVAD site.
- Perform hand hygiene and put on gloves.
- Assemble the supplies on a sterile field.
- Remove the existing dressing by lifting the edge of the dressing at the catheter hub and gently pulling it perpendicular to the skin toward the insertion site. Discard the dressing in an appropriate receptacle. Remove the engineered stabilization device and discard it.
- Assess the catheter-skin junction and surrounding skin. Inspect the catheter integrity.
- Remove gloves and perform hand hygiene.
- Don sterile gloves.
- Follow manufacturer's recommendations for appropriate cleansing products, application, and dry times. Always allow the product to dry naturally without wiping, fanning, or blowing on the skin.³ Cleansing products are typically applied using a back-and-forth motion while moving vertically and horizontally for at least 30 seconds. Apply a skin barrier solution, engineered stabilization device, and/or chlorhexidine-impregnated sponge according to the manufacturer's instructions.
- Apply a transparent semipermeable dressing over the catheter insertion site. Label the dressing with the date according to agency policy.
- Open the needleless connector package using sterile technique and

3. Gorski, L. A., Hadaway, L., Hagle, M. E., Broadhurst, D., Clare, S., Kleidon, T., Meyer, B. M., Nickel, B., Rowley, S., Sharpe, E., & Alexander, M. (2021). Infusion therapy standards of practice (8th ed.). *Journal of Infusion Nursing: The Official Publication of the Infusion Nurses Society*, 44(1S Suppl 1), S1–S224. <https://doi.org/10.1097/NAN.0000000000000396>

inspect the integrity of the device. Attach the prefilled 10-mL normal saline syringe and prime the connector.


- Ensure the clamp between the connector and the catheter is closed.
- Remove the existing needleless connector. Perform a vigorous scrub of the catheter hub per facility policy. Allow it to dry completely.
- Attach the new primed needleless connector to the catheter hub and rotate to tighten.
- Unclamp the catheter and aspirate for a blood return. If blood is aspirated, slowly inject the normal saline flush into the catheter using a pulsatile flushing technique.⁴
- Clamp the catheter and remove the syringe.
- Place a new antiseptic-impregnated sterile port cap on the needleless connector, if available.
- Dispose of used equipment in appropriate receptacles.
- Remove and discard gloves and other personal protective equipment, if worn.
- Perform hand hygiene.
- In an inpatient setting, help the client into a comfortable position and place personal items, the tray table, and the call light within easy reach. Make sure the client knows how to use the call light to summon assistance. To ensure the client's safety, raise the appropriate number of side rails and lower the bed to the lowest position. Ensure the bed is locked.
- Perform hand hygiene.
- Document the procedure and assessments.

Documentation Cues:

- Date/Time of procedure
- Condition and appearance of site, condition, and type of securement device, if used

4. Gorski, L. A., Hadaway, L., Hagle, M. E., Broadhurst, D., Clare, S., Kleidon, T., Meyer, B. M., Nickel, B., Rowley, S., Sharpe, E., & Alexander, M. (2021). Infusion therapy standards of practice (8th ed.). *Journal of Infusion Nursing: The Official Publication of the Infusion Nurses Society*, 44(1S Suppl 1), S1–S224. <https://doi.org/10.1097/NAN.0000000000000396>

- Measurement of catheter (if appropriate and performed)
- Number of lumens to the catheter
- Type of dressing applied with date/time
- ANTT technique and masking for the procedure were used
- Injection cap change and to which lumens and date/time of cap change
- Type of stabilization device used
- Client's tolerance of the procedure
- Teaching provided to the patient and family (if applicable), understanding, and follow-up teaching needed
- Any unexpected outcomes, if the health care provider was notified due to any complications, what interventions were provided to the client, and the client's response to treatment

View the following YouTube video⁵ showing an instructor  demonstration of changing a CVAD dressing and needless connectors.



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=450#oembed-1>

5. Chippewa Valley Technical College. (2023, January 5). *Changing a CVAD dressing and needless connectors* [Video]. YouTube. Video licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/). https://youtu.be/AGhezALw_Aw

4.5 Checklist: Obtain a Blood Sample From a CVAD

**Disclaimer: Always follow agency policy and manufacturer recommendations*

Checklist: Obtain a Blood Sample From a CVAD^{1,2}

- Verify the provider's order.
- Gather the necessary equipment:
 - Gloves
 - 10-mL prefilled syringes containing preservative-free normal saline flush solution (or syringes specifically designed to generate lower injection pressure)
 - Antiseptic pads or scrubs (chlorhexidine-based, povidone-iodine, or alcohol)
 - Appropriately sized syringes or needleless blood collection tube holder
 - Blood collection tubes
 - Labels
 - Laboratory biohazard transport bag
 - Puncture-resistant sharps disposal container
- Perform hand hygiene.
- Confirm the client's identity using at least two patient identifiers and check allergies.
- Provide privacy.
- Explain the procedure to the client and family (if appropriate) and answer any questions.
- Put on gloves and, if splashing is likely, put on a mask with a face shield or a mask and goggles.
- Raise the bed to waist level when providing care.
- Trace the tubing from the client to its point of origin.
- Stop any infusing IV fluids, including those running through another

1. *Clinical skills: Essentials collection* (1st ed.). (2021). Elsevier.

2. Lippincott procedures. <http://procedures.lww.com>

lumen of the catheter. Follow agency policy for how long the IV fluids must be stopped before the blood draw. Clamp the lumen, if appropriate. Detach the administration set from the needleless connector and place a sterile cap over the end of the administration set, if necessary.

- If no IV fluids are infusing and an antiseptic-impregnated sterile cap is covering the end of the needleless connector, replace it according to agency policy. For example, if drawing blood for blood cultures, agencies may require changing the cap before the blood draw to prevent contamination of blood culture results.
- Perform a vigorous mechanical scrub of the needleless connector for at least 15 seconds using an antiseptic pad. Allow it to air dry; do not fan or wave over it.
- While maintaining sterility of the syringe tip, attach a prefilled syringe containing preservative-free normal saline solution to the needleless connector. Unclamp the catheter and slowly aspirate for blood return. Troubleshoot if no blood return occurs; notify the practitioner if troubleshooting is ineffective.
- If blood return occurs, slowly inject the preservative-free normal saline solution into the catheter.
- Using the attached syringe used for flushing, aspirate the same volume of blood as amount of saline used to flush the catheter.
- Clamp the catheter and remove and discard the blood collection tube or syringe.
- Perform a vigorous mechanical scrub of the needleless connector for at least 15 seconds using an antiseptic pad, allow it to dry, connect an empty syringe to the catheter, release the clamp, and withdraw the blood sample.
- Clamp the catheter and remove the syringe.
- Change the needleless connector according to the manufacturer's instructions.
- Perform a vigorous mechanical scrub of the needleless connector for at least five seconds using an antiseptic pad; allow it to dry.
- While maintaining sterility of the syringe tip, attach the syringe containing preservative-free normal saline solution.

- Unclamp the catheter, slowly inject the preservative-free normal saline solution into the catheter, and then reclamp the catheter.
- Remove and discard the syringe.
- Continue the client's prescribed continuous IV infusion; if the client doesn't have a continuous infusion prescribed, proceed with locking the device if required by the facility. Discard the syringe.
- Place a new antiseptic-impregnated sterile cap, if available at the facility, on the needleless connector after locking it with saline.
- If blood was obtained using a syringe, use the blood transfer unit to transfer the blood into appropriate blood collection tubes.
- Label the samples in the presence of the client.
- Place all blood collection tubes in a laboratory biohazard transport bag and send them to the laboratory with a completed laboratory request form.
- Dispose of used equipment in appropriate receptacles.
- Remove and discard gloves and other personal protective equipment.
- Perform hand hygiene.
- In an inpatient setting, help the client into a comfortable position and place personal items, the tray table, and the call light within easy reach. Make sure the client knows how to use the call light to summon assistance. To ensure the client's safety, raise the appropriate number of side rails and lower the bed to the lowest position. Ensure the bed is locked.
- Perform hand hygiene.
- Document the procedure and assessments.

Documentation Cues:

- Date and time the blood sample was drawn
- Volume of blood withdrawn
- Lumen used if the client has a multi-lumen central venous access catheter
- Laboratory tests for which the sample was drawn
- Time the sample was sent to the laboratory
- Assessment of the catheter exit site and the patency of the catheter

- Absence of signs and symptoms of complications
- Presence of blood return on aspiration
- Lack of resistance when flushing
- Amount and types of flushes used
- Teaching provided to the client and family (if applicable), understanding, and follow-up teaching needed



View a YouTube video³ showing an instructor demonstration of this skill:



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=452#oembed-1>

3. Chippewa Valley Technical College. (2023, January 5). *Obtaining a blood sample from a central venous access device (CVAD)* [Video]. YouTube. Video licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/).

4.6 Checklist: Access an Implanted Venous Access Device

Checklist: Access an Implanted Venous Access Device^{1,2}

- Review the client's medical record for information about the implanted venous access device. Determine if the device is "power injectable."
- Ensure confirmation of catheter tip placement.
- Verify the provider's order if required by the facility.
- Determine whether the client has a history of allergies or contraindications to the antiseptic, anesthetic, or prescribed solution.
- Gather the necessary equipment:
 - Gloves
 - Masks
 - Sterile gloves
 - Sterile drape
 - Safety-engineered noncoring needle (smallest gauge necessary to accommodate the prescribed therapy and length that allows external components to sit level with the skin and securely within the implanted venous access device) with attached extension set tubing
 - Antiseptic pad or applicator (chlorhexidine-based, povidone iodine, or alcohol)
 - Sterile 10-mL syringes (or syringes specifically designed to generate lower injection pressure) prefilled with preservative-free normal saline solution
 - Sterile transparent semipermeable dressing (may be chlorhexidine-impregnated)
 - Sterile needleless connector
 - Securement device (follow agency policy)
- Perform hand hygiene.
- Confirm the client's identity using at least two patient identifiers and check allergies.

1. *Clinical skills: Essentials collection* (1st ed.). (2021). Elsevier.

2. Lippincott procedures. <http://procedures.lww.com>

- Provide privacy.
- Explain the procedure to the client and family (if appropriate) and answer any questions.
- Assess the client's pain tolerance and discuss preferences for using local anesthetic. If warranted, prepare and administer EMLA cream or intradermal lidocaine prior to accessing the implanted venous access device, as prescribed.
- Raise the client's bed to working level.
- Perform hand hygiene.
- Put on gloves.
- Ask the client to put on a mask and then position them for comfort with their head turned toward the opposite side of the implanted venous access device.
- Assess the skin overlying and surrounding the implanted venous access device. Report abnormal findings to the provider.
- Palpate and locate the septum; assess for device rotation.
- Remove and discard gloves.
- Perform hand hygiene.
- Put on a mask.
- Perform hand hygiene.
- Open the supplies and prepare a sterile field using a sterile drape. Using sterile technique, place the supplies on the sterile field.
- Perform hand hygiene.
- Put on sterile gloves.
- Clean the site of the implanted venous access device with an antiseptic solution following the manufacturer's instructions.
- Attach a needleless connector to the extension set attached to the noncoring needle.
- Maintaining sterility of the syringe tip, attach a syringe containing preservative-free normal saline solution to the needleless connector and prime the extension set and noncoring needle with preservative-free normal saline solution. Clamp the extension set tubing.
- Palpate and stabilize the implanted venous access device with the nondominant hand.

- Grasp the noncoring needle with the dominant hand and insert the noncoring needle perpendicular to the skin through the septum of the implanted venous access device until the needle tip comes in contact with the back of the implanted venous access device.
- Unclamp the extension tubing and aspirate for blood return and then flush the implanted venous access device with preservative-free normal saline solution.
- Secure the noncoring needle with an engineered-stabilization device. Support the wings of the noncoring needle with sterile gauze; make sure that the gauze doesn't prevent visualization of the needle insertion site.
- If applicable, place a chlorhexidine-impregnated sponge dressing beneath the needle, following the manufacturer's directions.
- Apply a sterile semipermeable transparent dressing over the insertion site, noncoring needle, and upper portion of the extension tubing.
- Label the dressing with the current date or the date the dressing change is due as directed by the facility.
- Discard the used supplies. Dispose of used equipment and waste in an appropriate receptacle.
- Remove and discard gloves and mask.
- Perform hand hygiene.
- In an inpatient setting, help the client into a comfortable position and place personal items, the tray table, and the call light within easy reach. Make sure the client knows how to use the call light to summon assistance. To ensure the client's safety, raise the appropriate number of side rails and lower the bed to the lowest position. Ensure the bed is locked.
- Perform hand hygiene.
- Document procedure and assessments.

Documentation Cues:

- Date and time
- Location appearance of the site
- Needle gauge and length
- Number of attempts to access implanted venous access device

- Any unexpected outcomes and interventions
- Amount and type of flush solution used
- Patency of the catheter
- Presence of blood return
- Lack of resistance when flushing
- Client's tolerance of the procedure
- Teaching provided to the client and family (if applicable), understanding of that teaching, and any need for follow-up teaching

View a YouTube video³ showing an instructor demonstration of this skill:



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=454#oembed-1>

3. Chippewa Valley Technical College. (2023, January 5). *Accessing an implantable port* [Video]. YouTube. Video licensed under CC BY 4.0. <https://youtu.be/BGOTSPZdFdE>

4.7 Documentation

Sample Documentation for a CVAD Dressing Change:

11/19/20XX 0900

Double lumen PICC line dressing was changed to the right upper arm using a prepackaged CVAD dressing kit. Old dressing was removed and discarded. Site is without redness, swelling, exudate, or indication of complications. Client denies discomfort at the insertion site or along the vein track. Pre-procedure, catheter measured 4 cm external from insertion site to hub, which corresponds to the initial insertion external measurement. Upper arm circumference 10 cm above insertion site is 23 cm, which corresponds to the previous shift's measurement of 23 cm. No visible swelling or subcutaneous emphysema is observed. Nurse and client donned sterile masks. Per sterile technique, site area was cleansed with chlorhexidine scrub for 30 seconds and allowed to air dry. Device secured with Statlock followed by chlorhexidine gel impregnated sterile transparent dressing. Line flushed freely with 10mL of sterile, preservative-free 0.9% normal saline after obtaining brisk blood return. Needleless injection ports x2 were replaced and passive caps x2 were changed. Post-procedure, catheter measured 4 cm external from insertion site to hub, which corresponds to the initial insertion external measurement. Dressing dated and labeled. Client tolerated the procedure well without complications.

Jane Smith, RN

4.8 Learning Activities

Exercises

(Answers to the exercises are located in the Answer Key at the back of the book).

Case Study #1

Autumn, age 32, has a history of Diabetes Mellitus Type II and has been admitted to the hospital with a left lower leg wound that developed cellulitis. She has been receiving antibiotic therapy in the hospital for the past two days through a right upper arm PICC line and is now ready for discharge. When at home, she will continue to receive cefazolin 500 mg IV every 8 hours for the next 14 days.

1. What will you provide for patient education for Autumn regarding her PICC line?
2. What are the maintenance care priorities for care of the PICC line?
3. Are there any specific concerns related to Autumn's need for a PICC line that should be monitored or addressed?
4. What is the purpose of the PICC line?
5. How often should a PICC line be assessed?
6. How does the dressing get changed for a PICC line?
7. What makes a PICC line different from a peripheral IV and from an implanted port?



An interactive H5P element has been excluded from this version of the text. You can view it online here:

<https://wtcs.pressbooks.pub/nursingadvancedskills/?p=458#h5p-10>



An interactive H5P element has been excluded from this version of the text. You can view it online here:


<https://wtcs.pressbooks.pub/nursingadvancedskills/?p=458#h5p-11>



An interactive H5P element has been excluded from this version of the text. You can view it online here:

<https://wtcs.pressbooks.pub/nursingadvancedskills/?p=458#h5p-12>



Test your knowledge using a NCLEX Next Generation-style  [question](#). You may reset and resubmit your answers to this question an unlimited number of times.

IV Glossary

Air embolism: The result of a pressure gradient that allows air to enter the bloodstream when flushing the catheter.

Aseptic-impregnated catheter hub: A specific device or product that has an aseptic particulate embedded within it to prevent biological contaminants from entering a susceptible host. An example of an aseptic-impregnated device is a chlorhexidine impregnated CVAD dressing.

Aseptic nontouch technique (ANTT): A global standard used to prevent healthcare-acquired infections. ANTT identifies key parts and key sites throughout the preparation and implementation of the procedure. A key part is any sterile part of equipment used during an aseptic procedure, such as needle hubs and dressings. A key site is the insertion site, nonintact skin, or an access site for medical devices connected to clients. ANTT includes four underlying principles to keep in mind while performing invasive procedures:

- Always perform meticulous hand hygiene.
- Never contaminate key parts.
- Touch nonkey parts with confidence.
- Take appropriate infection control precautions.

Central line-associated bloodstream infection (CLABSI): A laboratory-confirmed bloodstream infection not related to an infection at another site that develops within 48 hours of a central line placement. Most CLABSI cases are preventable with proper aseptic techniques, surveillance, and management strategies.

Central venous access device (CVAD): A central line is a thin, flexible, large-bore tube inserted into a client's large vein.

Central venous pressure (CVP): Pressure observed within the central veins as the veins enter the right atrium. Central venous pressure is a good indicator of right heart function and is often monitored during fluid resuscitation.

Extravasation: Leakage of fluid into the tissues around the IV site causing tissue injury when the catheter has dislodged from the blood vessel but is still in the nearby tissue.

Fluid resuscitation: Infusing a large volume of fluid through the intravenous venous access to restore hemodynamics and optimize tissue perfusion and, ultimately, tissue oxygen delivery.

Fluoroscopy: A medical procedure that makes a real-time video of the movements inside a part of the body by passing X-rays through the body over a period of time.

Flushing: A manual injection of 0.9% sodium chloride to clean the catheter.

Hemodynamic monitoring: The assessment of a critically ill client's circulatory status and includes measurements of central venous pressure, cardiac output, and blood volume.

Locking: The injection of a limited volume of a liquid following the catheter flush, for the period of time when the catheter is not used, to prevent intraluminal clot formation and/or catheter colonization.

Reservoir pocket: A small pocket, either a plastic or metal cylinder, usually placed just below the collar bone and connected to a catheter that enters a large vein such as the subclavian.

Scrub hub: A scrubbing device with an embedded alcohol product such as chlorhexidine with alcohol or 70% alcohol to disinfect catheter hubs or needleless connectors.

Vesicant medications: Certain medications such as antineoplastic drugs, antibiotics, electrolytes, and vasopressors that can cause severe tissue injury or destruction.

5.1 Introduction

Learning Objectives

- Identify the indications for NG tube insertion
- Identify contraindications for NG tube insertion
- Outline essential safety principles related to the insertion of an NG tube, including evidence-based placement verification
- Outline nursing assessments and interventions related to the insertion of an NG tube
- Use clinical judgment to prevent, assess, manage, and document complications related to NG tubes
- Demonstrate the procedures for insertion and discontinuation of an NG tube
- Describe client care considerations prior to and following NG insertion

Enteral tubes are tubes placed in the gastrointestinal tract for stomach decompression, as well as an alternate route for feeding and/or medication administration. **Stomach decompression** is a medical term that refers to removing stomach contents by using suctioning. Stomach decompression is commonly used after surgery or trauma to reduce pressure from the buildup of fluids and gas that cause pain, nausea, and vomiting that can lead to potential aspiration of stomach contents into the lungs.

Insertion and post-insertion care of enteral nasogastric feeding (NG) tubes are common procedures in the United States, with more than 1.2 million temporary nasogastric feeding tubes inserted annually.¹ Clients in acute care

1. Bloom, L., & Seckel, M. A. (2022). Placement of nasogastric feeding tube and postinsertion care review. *AACN Advanced Critical Care*, 33(1), 68–84. <https://doi.org/10.4037/aacnacc2022306>

and community settings may have various types of enteral tubes to assist their recovery. Nurses are involved in the insertion, management, and removal of NG tubes, as well as the administration of feedings and medications through NG tubes. They must understand the manner in which these devices work, their purpose, and ways to prevent complications. Although inserting an NG tube is a commonly performed procedure, it can cause significant risk to the client if performed improperly.

Nursing responsibilities associated with caring for a client with an enteral tube include the following:

- Assessing tube placement and patency
- Assessing and cleansing the insertion site
- Administering tube feeding
- Administering medication via the enteral tube
- Irrigating/flushing the tube
- Managing gastric tube suctioning
- Monitoring and responding to potential complications

This chapter will discuss indications and contraindications for NG tubes, review the anatomy and physiology related to NG tubes, outline techniques to verify NG tube placement, and discuss potential complications. Checklists for inserting and removing NG tubes are also provided.

- ▶ Review the “[Enteral Tube Management](#)” and “[Administration of Enteral Medications](#)” chapters in the *Open RN Nursing Skills* book for additional information about various types of enteral tubes and related nursing responsibilities.²

2. This work is a derivative of [Nursing Skills](#) by [Open RN](#) and is licensed under [CC BY 4.0](#)

5.2 Basic Concepts

A **nasogastric (NG) tube** is a flexible plastic tube inserted through a nostril, down the posterior oropharynx, and into the stomach or the upper portion of the small intestine. It is typically used for decompression of the stomach for clients with an intestinal obstruction or ileus or for administration of nutrition or medication to clients who are at risk for aspiration or unable to tolerate oral intake. Depending on the intended purpose of the tube, there are different types of NG tubes designed specifically for its use.¹




Orogastric (OG) tubes have similar indications, monitoring, and care as NG tubes, but they are inserted through the mouth instead of the nose. OG tubes are often preferred for clients receiving mechanical ventilation.

Anatomy and Physiology

The nurse should be familiar with the anatomy and physiology of the nose, pharynx, esophagus, and stomach when caring for clients with NG tubes. See Figure 5.1² for an illustration of the nasal cavity and pharynx.

1. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

2. "[Blausen_0872_UpperRespiratorySystem.png](#)" by Blausen.com staff (2014). "[Medical gallery of Blausen Medical 2014](#)" for WikiJournal of Medicine 1 (2). DOI:[10.15347/wjm/2014.010](#). ISSN [2002-4436](#) is licensed under [CC BY 3.0](#)



The Upper Respiratory System

Figure 5.1 Nasal Cavity, Pharynx, and Epiglottis

The nares are the exterior openings to the nasal cavity. Usually, one nare is larger and more patent than the other. A septum, composed of bone and cartilage, divides the right and left nasal cavities. The nasal floor is parallel to the roof of the mouth. The end of the nasal cavity is narrow and ends at the juncture of several bones, including a portion of the cribriform plate, which is a very thin bone that, if fractured, could provide a direct portal into the brain. For this reason, NG tube placement in clients with suspected head trauma may be contraindicated.

The pharynx is a mucous membrane lined tube that begins at the nasal cavity and is divided into three major regions: the nasopharynx, the oropharynx, and the laryngopharynx.

- The nasopharynx serves only as an airway. It is a muscular passageway at the beginning of the pharynx, located behind the nasal cavity. It curves to extend behind the oral cavity to become the oropharynx.
- The oropharynx is a passageway for both air and food. The oropharynx is bordered superiorly by the nasopharynx and anteriorly by the oral cavity.
- The laryngopharynx is inferior to the oropharynx and posterior to the larynx. It continues the route for ingested material and air to the inferior end where the digestive and respiratory systems diverge. Anteriorly, the laryngopharynx opens into the larynx, and posteriorly it enters the esophagus that leads to the stomach. The larynx connects to the trachea and the lungs, so for this reason, great care must be taken when inserting

an NG tube to ensure it enters the posterior laryngopharynx and goes into the esophagus, not anteriorly into the trachea and the lungs.

The epiglottis is a cartilaginous flap of connective tissue located at the entrance to the larynx. During swallowing, the larynx moves upward, and the epiglottis closes over the glottis to prevent aspiration of food and fluid into the trachea. Many clinicians use this natural movement during NG tube insertion by asking clients to swallow ice chips or water once the NG tube passes beyond the oropharynx (i.e., the back of the oral cavity). As the client swallows, the rising and falling of the larynx and the opening and closing of the epiglottis can assist passage of the NG tube beyond the laryngopharynx toward the esophagus. The nurse can request the client to tuck their chin to ease this passage.

The esophagus starts at the upper esophageal sphincter and runs down through the diaphragm past the lower esophageal sphincter to the stomach. See Figure 5.2³ for an illustration of the pharynx, trachea, esophagus, and stomach.




Figure 5.2 Pharynx, Trachea, Esophagus, and Stomach

3. "D_M3_24.jpg" by unknown Cenveo is licensed under [CC BY 3.0](https://creativecommons.org/licenses/by/3.0/). Access for free at <https://pressbooks.cconline.org/bio106/chapter/digestive-structures-and-functions/>

Indications for NG Tubes

These are the indications for NG tubes⁴:

- To decompress the stomach and gastrointestinal (GI) tract (i.e., to relieve distention due to bowel obstruction, ileus, or atony)
- To administer nutrition and/or medication
- To empty the stomach to prevent aspiration (for example, NG tubes may be inserted in intubated clients to prevent aspiration)
- To remove blood from clients with GI bleeding⁵
- To obtain a sample of gastric contents to assess bleeding, volume, or acid content
- To remove ingested toxins
- To give antidotes such as activated charcoal
- To give oral radiopaque contrast agents
- To provide bowel rest

Bowel Obstruction and Ileus

The most common indication for placement of a nasogastric tube is to decompress the stomach of a client with a distal bowel obstruction or ileus.

Bowel obstruction is a mechanical blockage of intestinal contents by a mass, adhesion, hernia, impacted stool, or other physical blockage such as volvulus (i.e., twisting of the stomach or intestine) or intussusception (i.e., one segment of intestine telescopes inside another). Bowel obstructions block the normal passage of bodily fluids such as salivary, gastric, hepatobiliary, and enteric secretions, causing the fluids to build up, resulting in abdominal distension, pain, and nausea. Eventually, the fluids will build up to a point that nausea will progress to emesis, putting the client at risk for aspiration.⁶

Ileus occurs when there is a nonmechanical decrease or stoppage of the flow of intestinal contents. Ileus is often an unavoidable consequence of

4. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

5. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

6. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

abdominal or retroperitoneal surgery but can also be found in severely ill clients with septic shock or mechanical ventilation. An ileus usually manifests itself from the third to the fifth day after surgery and usually lasts 2 to 3 days with the small bowel being the quickest to return to function (0 to 24 hours), followed by the stomach (24 to 48 hours), and lastly the colon (48 to 72 hours). Other causes of ileus may include the following⁷:

- Prolonged abdominal/pelvic surgery
- Lower gastrointestinal (GI) surgery
- Opioid use
- Intra-abdominal inflammation (sepsis/peritonitis)
- Peritoneal carcinoma
- Perioperative complications (pneumonia or abscess)
- Bleeding (intraoperative or postoperative)
- Hypokalemia
- Delayed enteral nutrition or nasogastric (NG) tube placement

NG tube placement is a temporary intervention for bowel obstruction and ileus when normal peristalsis is temporarily altered. It serves to decompress the stomach and keep it empty until normal peristalsis returns. If decompression is needed for more than six weeks, then something more permanent like a jejunostomy tube may be inserted.

Nutrition and Medication Administration

Nasogastric tubes may be placed to administer nutrition or medications for a client who has a functional GI tract but is unable to ingest, chew, or swallow food safely or in adequate amounts. This indication is common for clients who have suffered a cerebrovascular accident (i.e., stroke) that has left them unable to swallow effectively. Nasogastric tubes may be placed for nutritional support while waiting to see how much function the client will recover. If the client does not adequately recover their swallowing ability or will otherwise

7. This work is a derivative of [StatPearls](#) by Beach and De Jesus and is licensed under [CC BY 4.0](#)

require long-term nutritional support, then a more permanent feeding tube is placed such as a gastrostomy or jejunostomy feeding tube.⁸

Other examples of conditions where clients have a functioning GI tract but cannot tolerate oral intake are as follows:

- Decreased level of consciousness, such as a coma or a sedated client on a ventilator
- Following upper gastrointestinal surgery where an **anastomosis** (i.e., a surgical connection between parts of the intestine) must be protected in the initial postoperative period
- During preoperative period to prepare malnourished clients for major abdominal surgery

For many of these indications for NG tubes, an orogastric tube (OG tube) can also be placed. Many of the principles used to manage an NG tube are the same for managing an OG tube, such as checking placement and monitoring for potential complications.

Contraindications for NG Tubes

There are two types of contraindications for any procedure or intervention and are referred to as absolute and relative. An absolute contraindication means the procedure or intervention may produce a life-threatening situation and should be avoided if possible. A relative contraindication means caution should be used because the possibility of an adverse event is possible; therefore, benefits must outweigh the risks.

Absolute contraindications to the placement of an NG tube include significant facial trauma; basilar skull fractures; or recent nasal, throat, or esophageal surgery where attempted placement of a tube via the nares may exacerbate the existing tissue trauma. In some cases of esophageal surgery, such as an esophagectomy, the surgeon will place the NG tube in the operating room and then remove it when indicated; the nurse should not manipulate the NG tube in this case. Esophageal obstruction, such as a

8. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

neoplasm or foreign object, is also an absolute contraindication to nasogastric tube placement.⁹

Relative contraindications include esophageal trauma, especially if caustic substances were ingested. Coagulation abnormalities or anticoagulation therapy may cause bleeding from the tissue trauma from tube placement. For clients with previous gastric bypass surgery, hiatal hernia repair, or abnormal GI anatomy (such as esophageal varices or strictures), NG tubes should be placed by a provider under endoscopy.¹⁰

Types of NG Tubes

There are two basic types of NG tubes, those used for decompression and those used for feeding.

For decompression, a double-lumen, rigid tube is used with one large lumen used for suction and a smaller lumen to act as a sump. (A sump allows air to enter to prevent suctioning of the gastric mucosa into the eyelets at the distal tip of the tube or obstruction when the stomach is fully collapsed.) These tubes are often referred to as “Salem Sump.” Their bore size ranges from 6 to 18 French, with those most commonly inserted being 14 to 16 French. A blue pigtail on this type of tube is the air vent, so it should never be clamped, connected to suction, or used for irrigation. See Figure 5.3¹¹ for an image of a Salem Sump.

9. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

10. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

11. “11720205623covidien-salem-sump-nasogastric-suction-tube-P” by unknown author used on the basis of Fair Use.

Access original image at https://www.healthproductsforyou.com/p-covidien-salem-sump-nasogastric-suction-tube.html?utm_source=google&utm_medium=surfaces&utm_campaign=shopping%20feed&utm_content=free%20google%20shopping%20clicks&gclid=Cj0KQCQiAsdKbBhDHARIsANJ6-jcX4iGGwtT30nfQXurA9kiTlvlvBJONj6BXyuGL4mGAnc40lL0tdCQaArZzEALw_wcB




Figure 5.3 Salem Sump. Used under Fair Use.

NG tubes used for administration of medications or feeding are single lumen and are softer than those used for decompression. They have a smaller bore with a size ranging from 8 to 12 French. NG tubes placed for feeding or medication administration may be a Levin tube or a Dobhoff tube. A Levin tube is a simple small diameter NG tube. A Dobhoff tube is a special type of NG tube that is small-bore and flexible, so it is more comfortable for the client than a standard NG tube. The tube is inserted with the use of a guide wire, called a stylet, that is removed after correct tube placement is confirmed. A Dobhoff tube also has weight on the end to allow gravity and peristalsis to help advance the end of the tube past the pylorus, providing an additional barrier to reduce aspiration risk of nutrition or medications administered. See Figure 5.4¹² for an image of a Levin tube and Figure 5.5¹³ for an image of a Dobhoff tube.

12. "2-Levin-Tube.jpg" by unknown author is used under Fair Use. Access original image at <https://www.smd-medical.com/product-detail/levin-tube-stomach-tube/>

13. "COV711006CN_PRI03.JPG" by unknown author is used under Fair Use. Access original image at <https://punchout.medline.com/product/Kangaroo-Dobhoff-Tip-Nasogastric-Feeding-Tube/Nasogastric-Tubes/Z05-PF10706>




Figure 5.4 Levin Tube




Figure 5.5 Dobhoff Tube With Weighted Tip

NG Tube Insertion

Insertion of an NGT is typically a clean (not sterile), “blind” procedure, meaning the person performing the procedure can’t visualize where the tube is going in the client’s body as they are inserting it. Insertion involves passing the tube through the nose, along the nasal floor, through the pharynx and down the esophagus until the proximal tip of the tube rests in the client’s stomach. See “[Checklist: Insert a Nasogastric Tube](#)” for detailed procedural instructions.

NG tubes are inserted and removed by nurses and other health care providers. Due to the invasive nature of the placement process, privately ask the client if they desire visitors to leave the room during placement or removal of the NG tube. Nurses provide the daily care of NG tubes, as well as

the administration of nutritional formulas, medications, and other substances through the tube. Nursing management of NG tubes are further described in the “[Applying the Nursing Process](#)” section of this chapter. The nurse is also responsible for verifying the NG tube has been accurately placed prior to initial use and before each use thereafter.¹⁴

Estimating the Depth of NG Tube Placement

Five to seven centimeters posterior to the nares, the nasal sinus connects to the nasopharynx. The length of the pharynx from the base of the skull to the start of the esophagus is 12 to 14 centimeters. The esophagus, from the upper esophageal sphincter to the stomach, is approximately 25 centimeters. The stomach is a highly distensible structure and can vary in length, but the empty stomach is typically about 25 centimeters long. Thus, approximately 55 centimeters of the NG tube is typically inserted in an adult.¹⁵

There are several methods used to estimate the depth that an NG tube should be placed. A common preprocedural maneuver used to estimate the length of the tube that should be inserted is to measure the tube from the tip of the client’s nose to the earlobe and then against the throat down to the xiphoid process, about 1/2 inch to 1 inch below the sternal notch.¹⁶

Special Circumstances

Insertion of weighted NG tubes used for feeding, as well as NG tubes for post-GI surgery clients, is performed by specially trained advanced practice nurses, physician assistants, or physicians.

The NG tube inserted for a post-GI surgery client should never be repositioned due to the risk of rupturing a suture line. If the NG tube becomes dislodged, the surgeon should be notified.

If a client is unconscious, gag reflex should be assessed before initiating the

14. Patient Safety Movement. (2020). *Actionable patient safety solutions (APSS) #15: Nasogastric tube (NGT) placement and verification*. <https://patientsafetymovement.org/wp-content/uploads/2017/10/APSS-15-4.pdf>

15. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

16. Nasogastric or orogastric tube insertion. (2021). Lippincott procedures. <http://procedures.lww.com>

procedure. Flex their head forward with your nondominant hand during the procedure as the tube is passed through the larynx. Extra precautions must be taken for clients with head injury to avoid misplacement of the NG tube.

Request assistance prior to starting the procedure based on the client condition. For example, clients who are confused, anxious, at risk for pulling out the tube as it is being inserted, and children often require assistance. Additionally, for pediatric clients it is often helpful to have their parents or caregivers at the bedside. For infants, sucrose may be administered to alleviate discomfort, based on agency policy.

Verifying NG Tube Placement

Insertion of NG tubes is considered a simple procedure, but incorrect placement can lead to client harm and possibly death. The risk of harm and death increases when misplaced tubes are not identified prior to their use. For this reason, placement must be verified immediately after insertion by an X-ray to ensure it has not been inadvertently placed into the trachea and into the bronchi. The nurse should monitor for signs and symptoms of incorrect placement during the procedure, such as coughing, decreased pulse oximetry readings, and cyanosis. If these signs occur, the tube should immediately be withdrawn until normal breathing resumes. See Figure 5.6¹⁷ for an image of an X-ray demonstrating correct placement of an enteral tube in the stomach as indicated by the lower red arrow. (This X-ray also demonstrates an endotracheal tube correctly placed in the trachea as indicated by the top arrow.) After X-ray verification, the tube should be marked with adhesive tape and/or a permanent marker to indicate the measurement on the tube where the feeding tube enters the nares or penetrates the abdominal wall. This number on the tube at the entry point should be documented in the medical record and communicated during handoff reports. At the start of every shift, the nurse should evaluate if the incremental marking or external tube length has changed. If a change is observed, bedside tests such as visualization or pH testing of tube aspirate

17. "ETTubandNGtubeMarked.png" by James Heilman, MD is licensed under [CC BY-SA 4.0](https://creativecommons.org/licenses/by-sa/4.0/)

can help determine if the tube has become dislodged. If in doubt, the provider should be notified and an X-ray repeated to confirm tube location.¹⁸




Figure 5.6 Placement Verification by X-Ray

After the tube placement is initially verified by X-ray, it is possible for the tube to migrate out of position due to the client coughing, vomiting, and moving. For this reason, the nurse must routinely check tube placement before every use. The American Association of Critical-Care Nursing recommends that the position of a feeding tube should be checked and documented every four hours and prior to the administration of enteral feedings and medications by

18. Boullata, J. I., Carrera, A. L., Harvey, L., Escuro, A. A., Hudson, L., Mays, A., McGinnis, C., Wessel, J. J., Bajpai, S., Beebe, M. L., Kinn, T. J., Klang, M. G., Lord, L., Martin, K., Pompeii-Wolfe, C., Sullivan, J., Wood, A., Malone, A., & Guenter, P. (2017). ASPEN safe practices for enteral nutrition therapy. *Journal of Parenteral and Enteral Nutrition*, 41(1), 15-103. <https://doi.org/10.1177/0148607116673053>

measuring the visible tube length and comparing it to the length documented during X-ray verification.^{19, 20, 21}

Older methods of verifying tube placement included observing aspirated GI contents or administering air into the tube with a syringe while auscultating (commonly referred to as the “whoosh test”). However, research has determined these methods are unreliable and should no longer be used to verify placement.^{22, 23}

Assessing the pH of aspirated gastric contents is a method used to verify placement in some agencies. Gastric aspirate should have a pH of less than or equal to 5.5 using pH indicator paper that is marked for use with human aspirate. However, caution should be used with this method because enteral formula and some medications alter the gastric pH.²⁴

Follow agency policy for assessing and documenting tube placement. Additionally, if the client develops respiratory symptoms that indicate potential aspiration, immediately notify the provider and withhold enteral feedings and medications until the placement is verified.

Potential Complications

The most common complications related to the placement of nasogastric tubes are discomfort, sinusitis, or epistaxis, all of which typically resolve

19. Boullata, J. I., Carrera, A. L., Harvey, L., Escuro, A. A., Hudson, L., Mays, A., McGinnis, C., Wessel, J. J., Bajpai, S., Beebe, M. L., Kinn, T. J., Klang, M. G., Lord, L., Martin, K., Pompeii-Wolfe, C., Sullivan, J., Wood, A., Malone, A., & Guenter, P. (2017). ASPEN safe practices for enteral nutrition therapy. *Journal of Parenteral and Enteral Nutrition*, 41(1), 15-103. <https://doi.org/10.1177/0148607116673053>
20. Lemyze, M. (2010). The placement of nasogastric tubes. *CMAJ: Canadian Medical Association Journal*, 182(8), 802. <https://doi.org/10.1503/cmaj.091099>
21. Simons, S. R., & Abdallah, L. M. (2012). Bedside assessment of enteral tube placement: Aligning practice with evidence. *American Journal of Nursing*, 112(2), 40-46. <https://doi.org/10.1097/01.naj.0000411178.07179.68>
22. Boullata, J. I., Carrera, A. L., Harvey, L., Escuro, A. A., Hudson, L., Mays, A., McGinnis, C., Wessel, J. J., Bajpai, S., Beebe, M. L., Kinn, T. J., Klang, M. G., Lord, L., Martin, K., Pompeii-Wolfe, C., Sullivan, J., Wood, A., Malone, A., & Guenter, P. (2017). ASPEN safe practices for enteral nutrition therapy. *Journal of Parenteral and Enteral Nutrition*, 41(1), 15-103. <https://doi.org/10.1177/0148607116673053>
23. Simons, S. R., & Abdallah, L. M. (2012). Bedside assessment of enteral tube placement: Aligning practice with evidence. *American Journal of Nursing*, 112(2), 40-46. <https://doi.org/10.1097/01.naj.0000411178.07179.68>
24. Best, C. (2019). Selection and management of commonly used enteral feeding tubes. *Nursing Times*, 115(3), 43-47. <https://www.nursingtimes.net/clinical-archive/nutrition/selection-and-management-of-commonly-used-enteral-feeding-tubes-18-02-2019/>

spontaneously with the removal of the nasogastric tube.²⁵ Other complications associated with use of an NG tube range from minor to more severe and may include the following conditions:

- Trauma to the nares, larynx, esophagus, and/or stomach during insertion.
- Trauma to or erosion of gastric mucosa, especially if gastric suctioning is prolonged.
- Mucosal pressure injury of the nares.
- Placement-related issues: Inadvertent placement in the trachea that can lead to pleural injury, pneumothorax, tracheobronchial aspiration, pneumonia, and death. Respiratory distress is a medical emergency, and emergency assistance must be obtained immediately.
- Esophageal perforation, evidenced by neck or chest pain, dysphagia, dyspnea, subcutaneous emphysema, or hematemesis.
- Inadvertent intracranial placement through a fractured cribriform plate.
- Knotting of the NG tube around an endotracheal tube or retrograde positioning (i.e., the proximal tip of the tube curves upward through the esophagus).

25. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

5.3 Applying the Nursing Process

Assessments and Interventions Prior to Insertion of an NG Tube

Prior to the insertion of an NG tube, the following nursing assessments and interventions should be performed:

- Review agency policy for inserting and verifying placement of an NG tube.
- Verify the provider's orders.
- Review laboratory results to check for coagulopathies or blood dyscrasias. If the client is on anticoagulation therapy, assess their most current INR before performing the procedure and notify the provider of any concerns.
- Ask the client if they have any allergies (e.g., to latex, medications, or other substances).
- Confirm client history for facial trauma, deviated septum, nasal fractures, or risk of increased intracranial pressure.
- Assess the client's level of consciousness and their ability to participate in the procedure. Request assistance from a colleague as indicated.
- Perform a focused abdominal assessment to identify the client's baseline status. Auscultate bowel sounds and palpate the abdomen for distention, pain, or rigidity.
- Assess the nares for obstructions and the surrounding skin. Select the nostril with the best airflow and skin condition.
- Provide patient education on the procedure and answer questions.
- Provide emotional support and comfort while being aware this is an uncomfortable procedure for the client. It is helpful to have an assistant nearby during this procedure; the assistant can also provide emotional support to the client as needed during the procedure.

Expected Outcomes of the Procedure

These are the expected outcomes related to insertion of an NG tube:

- The NG tube is placed without causing trauma.
- The correct placement of an NG tube is verified according to agency policy.
- The NG tube remains in place, patent, and functional for the duration of therapy.

Assessments and Interventions After Insertion of the NG Tube

Assessments and interventions immediately after insertion of an NG tube include the following¹:

- Observe for signs of misplacement post-insertion, such as circumoral cyanosis, coughing, choking, dyspnea, decreased oxygen saturation level, or vomiting.
 - Respiratory distress is a medical emergency, and emergency assistance should be obtained.
 - Strongly consider removing the NG tube if these signs are present as the tube may be lodged in the airway or lungs.
- Do not administer fluids or medications via the NG tube until accurate placement has been verified with an X-ray.
- Document the following information in the client's medical record²:
 - Time and date of the procedure
 - Type and diameter of the NG tube
 - Number on the tube where it enters the nares and verification that number was communicated during handoff reports
 - Method(s) used to verify tube placement
 - Color and consistency of aspirate, including pH of aspirate if assessed
 - Client's tolerance of the procedure
 - Any unexpected client events or outcomes, interventions performed,

1. Lippincott procedures. <http://procedures.lww.com>

2. Walsh, K., & Schub, E. (2016). *Nasogastric tube: Inserting and verifying placement in the adult patient*. Cinahl Information Systems, Ebsco. https://www.ebscohost.com/assets-sample-content/Nasogastric_Tube_Insertion.pdf

and notification of the provider

- Patient/family education, including topics presented, response to education provided/discussed, and the plan for follow-up education

Routine Nursing Care of Clients with NG Tubes

Clients with NG tubes are at constant risk for developing adverse effects. While caring for clients with NG tubes, nurses monitor risks and adopt strategies for client safety and quality of care.

When working with clients who have NG tubes, nurses perform the following interventions³:

- **Keep the head of the bed 30 degrees or higher.**
 - Clients with NG tubes are at risk for aspiration, especially if they are receiving enteral nutrition. The head of the bed should always be raised 30 degrees or higher to prevent aspiration.
- **Prevent migration and/or dislodgement of the tube.**
 - The NG tube should be fastened to the client using a securement device and taped/pinned to the client's gown to prevent the tube from slipping from out of the stomach, migrating into the lungs, or being accidentally removed.
- **Maintain and promote comfort.**
 - The NG tube constantly irritates the client's nasal mucosa and can cause discomfort and potential skin breakdown. Ensure that the tube is securely anchored to the client's nose to prevent excess tube movement and is pinned to the gown in a manner that avoids excessive pulling or dragging. Routinely confirm the NG tube is not pressing against the client's nares or septum and regularly assess the skin around the tube and securement device for breakdown. The tube should be periodically repositioned in the nares to help prevent pressure injuries. Notify the provider of any concerns.

- If the client has abdominal distension or complains of abdominal pain, discomfort, or nausea or begins to vomit, perform the following actions:
 - If the client is receiving suctioning, verify suction settings are consistent with the provider order, including “continuous” versus “intermittent” suctioning and “low” versus “high” suction level. Check for kinking of the tube from the nare to the suction source.
 - Some NG tubes have valves that permit delivery of oral agents without disconnecting the tube. Ensure the valve is not turned in a direction that is blocking the tube.
- Assess the patency of a tube according to agency policy, typically by irrigating with a 60-mL syringe and 30 mL of tap water. NG tubes are prone to clogging for a variety of reasons. The risk of clogging may result from tube properties (such as narrow tube diameter), the tube tip location (stomach vs. small intestine), insufficient water flushes, aspiration for gastric residual volume, contaminated formula, and/or incorrect medication preparation and administration. To prevent clogging, NG tubes should be flushed a minimum of once per shift or according to provider orders/agency policy. Feeding tubes should be flushed immediately before and after intermittent feedings and medication administration and follow appropriate medication administration practices. Read more information about tube irrigation in the “[Basic Concepts of Enteral Tubes](#)” section in the *Open RN Nursing Skills* book.
- If the client is receiving enteral feedings, monitor for signs of tube feeding intolerance (i.e., abdominal bloating, nausea, vomiting, diarrhea, cramping, and constipation). If cramping occurs during bolus feedings, it can be helpful to administer the enteral nutritional formula at room temperature to minimize or help prevent symptoms.

- **Perform oral care.**

- Because one nostril is blocked, clients tend to breathe through their mouth, causing dehydration of the nasal and oral mucosa. Clients often complain of thirst, but they are typically NPO (nothing by mouth) when an NG tube is in place. Oral care keeps the oral mucous membranes moist and helps relieve dryness, as well as preventing infection. Oral care can include rinsing the mouth with cold water or mouthwash, as long as the client does not swallow. Some clients may be permitted to suck on ice chips per provider orders. Lubricant should be applied to the lips and the external nares.
- Clients may have throat discomfort. Some providers may prescribe a numbing throat spray but use with caution because it can hinder the gag reflex and increase the risk of aspiration.
- **Monitor input/output, electrolyte balances, and weight trend.**
 - Because a client with an NG tube is typically NPO, it is important to closely monitor their fluid, electrolyte, and nutritional statuses. They are also at risk for acid/base imbalance. NG tubes used for suctioning place clients at risk for hypokalemia and metabolic alkalosis when large volumes of stomach acid contents are removed from the body.
 - If the client is receiving suctioning, the drainage amount and color should be documented every shift.
 - Fluid flushes and enteral feedings should be documented in the Input and Output (I & O) area in the medical record.
 - Electrolyte and blood glucose levels should be monitored, as ordered, for signs of imbalances.
 - Daily weights are typically ordered, and weight trends should be monitored by the nurse.
- **Monitor for potential complications.**
 - Signs of tube dislodgement into the respiratory tract include coughing, shortness of breath, adventitious lung sounds, or decreasing oxygen saturation levels.

- Signs of esophageal perforation include neck or chest pain, dysphagia, dyspnea, subcutaneous emphysema, or hematemesis.

Life Span Considerations

When caring for older adults or children with NG tubes, there are additional factors to consider. For example, if the client wears dentures, remove them for the client's safety and comfort prior to inserting the NG tube.

For pediatric clients, irrigation of an NG tube requires a smaller fluid volume. Check agency policy, but typically the flushing volume is 2 to 5 mL in pediatric patients and 1 mL or less of water in neonates. For neonates, care should be taken to use the appropriate size and type of NG tube to prevent injury to the delicate nasal and gastrointestinal tissues.⁴

Delegation and Collaboration

The task of inserting and maintaining an NG tube cannot be delegated to unlicensed assistive personnel (UAP). However, the nurse can delegate the following actions to UAP under appropriate supervision:

- Measuring and recording drainage
- Providing oral and nasal hygiene
- Anchoring the NG tube to the client's gown during routine care to prevent displacement
- Immediately reporting to the nurse any signs of redness or irritation of the nares

Removal of NG Tube

See "[Checklist: Remove an NG Tube](#)" for procedural steps of removing an NG tube.

4. Institute of Safe Medication Practices. (2022). *Preventing errors when preparing and administering medications via enteral feeding tubes*. <https://www.ismp.org/resources/preventing-errors-when-preparing-and-administering-medications-enteral-feeding-tubes>.

Note that accidental removal of an NG tube is not a medical emergency. If accidental removal occurs, assess the client and notify the provider.

5.4 Checklist: Insert a Nasogastric Tube

**Disclaimer: Always follow agency policy and manufacturer recommendations*

Checklist: Insert a Nasogastric Tube^{1,2}

Preparation Before Procedure

The following steps should be taken in preparation for the procedure³:

- The indication for the procedure, potential complications, and alternative to treatment should be explained to the client by the provider. If an informed consent form is required by agency policy, the nurse should ensure the informed consent form has been signed and is present in the client's medical record.
- Review the client's medical record for conditions that may contraindicate insertion of an NG tube (e.g., facial trauma or fractures, deviated or swollen nasal septum).
- If the nasogastric tube is to be connected to suction, attach the NG tube to the suction tubing and suction container before placement of the tube to minimize the risk of spillage of gastric contents.
- Perform a thorough gastrointestinal (GI) assessment.
- Gather and prepare equipment. All supplies should be close at hand to minimize unnecessary movement during the procedure. *Note: Topical use of local anesthetics such as lidocaine has not been shown to be useful for NG insertion, but the evidence does show that nebulized lidocaine relieves discomfort and allows for an increased chance of NG tube placement.
- Gather the necessary supplies:
 - Nasogastric tube per provider order
 - Antireflux valve
 - Stethoscope
 - Pulse oximeter

1. *Clinical skills: Essentials collection* (1st ed.). (2021). Elsevier.

2. Lippincott procedures. <http://procedures.lww.com>

3. This work is a derivative of [StatPearls](#) by Sigmon and An and is licensed under [CC BY 4.0](#)

- Hypoallergenic tape or agency approved securement device
- Cup of water and straw
- Clean gloves
- Suction equipment (if prescribed by provider)
- Penlight
- Tongue blade
- Water-based lubricant
- Oral hygiene supplies
- Fluid-impermeable drape or towel
- Explain the procedure to the client and family members (if appropriate) according to their individual communication and learning needs. Assess client anxiety regarding insertion of the tube. Answer any questions and provide emotional support as necessary.

Procedure

- Verify the provider's orders for tube insertion and associated premedications.
- Perform hand hygiene.
- Confirm the client's identity using at least two patient identifiers and check allergies.
- Provide privacy.
- Assess the rigidity of the tube. If you need to increase the tube's flexibility to ease insertion, coil it around gloved fingers for a few seconds or dip it in warm water. If the tube is too flaccid, stiffen it by filling the tube with water and then freezing it or dipping the tube in ice water.
- Advise the client they may feel some discomfort as the tube moves through the nose but that the tube will be lubricated to ease its passage. Topical anesthetic and nasal vasoconstricting medications may be administered, as prescribed.
- Explain to the client they will be given water to sip once the tube reaches the pharynx. The swallowing action will facilitate passage of the tube and minimize the natural tendency to gag.
- Ask the client to identify a signal they will use to communicate with you if it is necessary to stop briefly during the insertion, such as raising their

hand.

- Raise the bed to waist level.
- Perform a focused gastrointestinal assessment.
- Because the dominant hand will be used to insert the tube, stand on the client's right side if right-handed or on the client's left side if left-handed.
- Position the client (in high Fowler's position) with the head of the bed elevated at least 30 degrees; if this position is contraindicated, consider the reverse Trendelenburg position. Assist the client in positioning their head in a neutral position, neither tilted forward nor backward.
- Perform hand hygiene.
- Put on nonsterile gloves and other personal protective equipment as indicated.
- Assess the client's nares to determine the best choice for insertion. Use a penlight to visualize nares as needed.
- Estimate the insertion length of the tube by measuring from the tip of the nose to the earlobe to the sternal notch of the xiphoid process. Mark this estimated exit point on the tube with a piece of tape or permanent marker.
- Drape a fluid-impermeable pad or towel over the client's chest. Place an emesis basin within reach because the client may gag or vomit during the procedure.
- Lubricate the proximal tip of the tube about 2 to 3 inches with water-soluble lubricant.
- Encourage the client to hold their head upright. You may wish to support the client's head with your nondominant hand while inserting the NG tube.
- Grasp the end of the tube with the distal end pointing downward, curve it if necessary, and carefully insert it into the most patent nare.
- Guide the tube at an angle parallel to the floor of the nasal canal and then gently downward as the tube advances through the nasal passage toward the distal pharynx.
- If resistance is met, try to gently rotate the tip until it advances past the nasal passage. If continued resistance is met, don't force the tube. Instead, withdraw the tube and allow the client to rest, relubricate the

tube, and retry or insert the tube in the other nare.

- After the tube reaches the oropharynx, have the client flex their head forward and tuck their chin down. Encourage them to sip water through a straw as you slowly advance the tube (unless contraindicated).
- As the tube is advanced, monitor the client for cues that might indicate that the tube entered the respiratory tract or the tube kinked or coiled in the oral cavity. If the client appears cyanotic or begins coughing severely during advancement of the tube, pull the NG tube backwards until normal breathing resumes. Severe coughing during tube insertion can indicate inadvertent placement in the trachea or bronchi. Reattempt advancement of the tube after the client begins breathing normally. However, never advance the NG tube against resistance because perforation may occur.
- Continue to advance the tube to the predetermined measured length.
- Following insertion, clean any excess lubricant from the client's skin.
- Secure the NG tube to the client's nose using a securement device, tape, or semipermeable transparent dressing. When securing the NG tube, use care to avoid applying undue pressure to tissue to reduce the risk of pressure injuries.
- Position the NG tube so the distal end is facing upwards and secure it to the client's gown according to agency policy. If using a rubber band, place it over the NG tube. Wrap one end of the rubber band behind the NG tube and up through the open half of the rubber band and then continue to pull the end so that the band is tightened around the tube. Use a safety pin to attach the rubber band and NG tube to the client's gown.
- Remove and discard the fluid-impermeable pad or towel.
- Discard used supplies in the appropriate receptacle.
- Remove and discard gloves and any personal protective equipment worn.
- Perform hand hygiene.
- Follow agency policy to verify correct placement of the NG tube. Do not instill anything through the NG tube or connect it to suction until correct placement has been confirmed.
- After correct placement is verified, document the length of the tube where it exits the nare. If a stylet is present, remove it at this point. Turn on

suction, if ordered, to intermittent or continuous suction and typically set it to 30 to 40 mmHg. Ensure the suctioning equipment is working properly.

- Provide oral care, discard any used supplies, and then perform hand hygiene.
- Keep the head of the bed elevated at least 30 degrees.
- In an inpatient setting, help the patient into a comfortable position and place personal items, the tray table, and the call light within easy reach. Make sure the patient knows how to use the call light to summon assistance. To ensure the patient's safety, raise the appropriate number of side rails and lower the bed to the lowest position. Ensure the bed is locked.
- Assess the client's status and comfort level; reposition as necessary.
- Update the client's plan of care, as appropriate.
- Perform hand hygiene.
- Document the procedure.

Documentation Cues:

- Pre-procedure assessments
- Type and size of tube placed
- Location of the distal tip of the tube (external measured length of the tube)
- Client's tolerance of the procedure
- Confirmation of the tube's position by X-ray examination
- Any unexpected outcome and related nursing interventions performed
- Pain assessment and management



View a YouTube video⁴ showing an instructor demonstration of this skill:



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=392#oembed-1>

4. Chippewa Valley Technical College. (2023, January 5). *Inserting a nasogastric tube* [Video]. YouTube. Video licensed under CC BY 4.0. <https://youtu.be/QA5lpxdbBQ>

5.5 Checklist: Remove an NG Tube

**Disclaimer: Always follow agency policy and manufacturer recommendations*

Checklist: Remove an NG Tube^{1,2}

Note: An NG tube should be removed if it is no longer required. The removal process is typically quick. Prior to removing an NG tube, verify the provider's orders for removal. If the NG tube was ordered to remove gastric content, the provider's order may include a "trial" clamping of the tube for a specified number of hours to verify the client can tolerate its removal. During the trial, the client should not experience any nausea, vomiting, or abdominal distension.³

- Verify the provider's orders to remove the NG tube.
- Gather the necessary supplies:
 - Fluid-impermeable pads
 - 20-60 mL syringe
 - Nonsterile gloves
 - Stethoscope
 - Oral hygiene supplies
 - Tissues
 - Garbage bag
- Verify the client using two patient identifiers.
- Explain the procedure to the client.
- Place the client in high Fowler's position.
- Perform hand hygiene.
- Assess the client's gastrointestinal function prior to removing the NG tube.
- Place a fluid impermeable pad on the client's chest.
- Disconnect the tube from feeding and suctioning if present.

1. *Clinical skills: Essentials collection* (1st ed.). (2021). Elsevier.

2. Lippincott procedures. <http://procedures.lww.com>

3. This work is a derivative of [Clinical Procedures for Safer Patient Care](#) by British Columbia Institute of Technology and is licensed under [CC BY 4.0](#)

- Remove the tape or securement device from the nose.
- Unclip the NG tube from the client's gown.
- Verify tube placement and then clear the NG tube by inserting 10 to 20 mL of air into the tube to prevent aspiration of any remaining gastric contents.
- Instruct the client to take a deep breath and hold it.
 - Holding one's breath closes the epiglottis and prevents aspiration.
- Kink the NG tube near the nare and gently pull out the tube in a swift, steady motion, wrapping it in your hand as it is being pulled out. Inspect the tube for intactness. Dispose of the tube in the garbage bag.
 - Kinking the tubing prevents any residual gastric contents from flowing out of the tube upon removal.
- Offer tissue and/or clean the nares for the client.
- Offer oral care for client comfort and to prevent transmission of microorganisms.
- Discard used supplies, remove gloves, and perform hand hygiene.
- In an inpatient setting, help the patient into a comfortable position and place personal items, the tray table, and the call light within easy reach. Make sure the patient knows how to use the call light to summon assistance. To ensure the patient's safety, raise the appropriate number of side rails and lower the bed to the lowest position. Ensure the bed is locked.
- Perform hand hygiene.
- Document the procedure and assessments.
- After tube removal, continue to monitor the client for signs of gastrointestinal (GI) dysfunction, including nausea, vomiting, abdominal distention or discomfort, and food intolerance. Notify the provider of GI dysfunction because reinsertion of the NG tube may be required.

Documentation Cues:

- Client's GI assessment and status before tube removal
- Date and time of NG tube removal; the color, consistency, and any amount of gastric drainage

- Visual inspection and intactness of the tube upon removal
- Client tolerance of the procedure
- Client and family (if applicable) education, their understanding of that teaching, and any need for follow-up teaching.
- Any type of unexpected outcome and the interventions performed



View a YouTube video⁴ showing an instructor demonstration of this skill:



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=394#oembed-1>

4. Chippewa Valley Technical College. (2023, January 5). *Removing a nasogastric tube* [Video]. YouTube. Video licensed under CC BY 4.0. <https://youtu.be/BYM1nOdIzoM>

5.6 Documentation

Sample Documentation:

11/17/20XX 1030

The NG tube insertion procedure was explained to the client. Prior to the NG tube insertion, hypoactive bowel sounds were present in all 4 quadrants, and the abdomen was slightly distended with no tenderness noted upon palpation. Client reported nausea and bloating. A 14 French, Salem NG tube was inserted via the left nostril at 1008 on 11/17/20XX. Placement was verified by X-ray and then the NG tube was attached to low intermittent suction as ordered. Tube was secured to the nose with exit point at 53 cm. Gastric drainage was pale green with pH of 4. Client tolerated the procedure without complication and reports decreased nausea. Client is resting comfortably in bed with no complaints of pain.

Jaimie Salvator, RN

5.7 Learning Activities

Exercises

(Answers to the exercises are located in the Answer Key at the back of the book).

Case Study #1

Caroline, age 92, visits her health care provider for a follow-up visit with her son Brian. You take Caroline's vitals prior to the visit and find her to be hypotensive and bradycardic. She is slow to respond to questions, and Brian answers most of the questions you have for her. Brian says, "I'm worried about mom; that's why I asked for this appointment. I haven't seen her since Christmas two weeks ago, but she looks as if she has withered away to nothing in that time."

You note that since her last visit six months ago, she has had a 20-pound weight loss, and her BMI today is 16.2. Caroline lives alone in an apartment in an assisted living facility; her husband passed five years ago. Brian is her only child.

Brian states, "I thought she was doing so well. I haven't been told that she wasn't eating, but when I visited yesterday, she refused to eat any lunch or dinner, and only ate a half piece of toast at breakfast."

When you ask Caroline how she's feeling, she says, "I just don't feel like eating anymore. I know that I'm healthy, but my appetite is not there. I'm not ready to give up." She smiles, "I'm still a feisty 92 years young."

Caroline's health care provider admits her to the hospital to start NG tube feedings.

1. What can you provide for client education regarding the NG tube?
2. What are the maintenance care priorities for care of the NG tube?
3. Are there any specific concerns related to Caroline's need for an NG tube that should be monitored or addressed? What will you consider as you prepare for placement of the NG tube?
4. What is the purpose of the NG tube?
5. How often should an NG tube be assessed?
6. What cues would indicate further assessment of the NG tube and the client?
7. What type of technique is used to insert the NG tube?



An interactive H5P element has been excluded from this version of the text. You can view it online here:

<https://wtcs.pressbooks.pub/nursingadvancedskills/?p=399#h5p-13>



An interactive H5P element has been excluded from this version of the text. You can view it online here:


<https://wtcs.pressbooks.pub/nursingadvancedskills/?p=399#h5p-14>



An interactive H5P element has been excluded from this version of the text. You can view it online here:

<https://wtcs.pressbooks.pub/nursingadvancedskills/?p=399#h5p-15>



Test your knowledge using a NCLEX Next Generation-style  [question](#). You may reset and resubmit your answers to this question an unlimited number of times.

V Glossary

Anastomosis: A surgical connection between parts of the intestine.

Bowel obstruction: A mechanical blockage of intestinal contents by a mass, adhesion, hernia, impacted stool, or other physical blockage such as volvulus (i.e., twisting of the stomach or intestine) or intussusception (i.e., one segment of intestine telescopes inside another). Bowel obstructions block the normal passage of bodily fluids such as salivary, gastric, hepatobiliary, and enteric secretions, causing the fluids to build up, resulting in abdominal distension, pain, and nausea.

Enteral tubes: Tubes placed in the gastrointestinal tract.

Ileus: A nonmechanical decrease or stoppage of the flow of intestinal contents that is often an unavoidable consequence of abdominal or retroperitoneal surgery.

Nasogastric (NG) tube: A flexible plastic tube inserted through a nostril, down the posterior oropharynx, and into the stomach or the upper portion of the small intestine. It is typically used for decompression of the stomach for clients with an intestinal obstruction or ileus or for administration of nutrition or medication to clients who are unable to tolerate oral intake.

Stomach decompression: A medical term that refers to removing stomach contents by using suctioning. Stomach decompression is commonly used after surgery or trauma to reduce pressure from the buildup of fluids and gas that cause pain, nausea, and vomiting and can lead to potential aspiration of stomach contents into the lungs.

PART VI

CHAPTER 6 MANAGE CHEST TUBE DRAINAGE SYSTEMS

Learning Objectives

- Describe the physiology of breathing and the importance of negative pressure
- Identify indications for chest tube placement
- Differentiate the basic compartments of a chest tube drainage system
- Describe the safety principles essential for chest tube maintenance
- Prioritize methods for troubleshooting chest tube drainage systems
- Outline nursing assessments related to caring for a client with a chest tube
- Prioritize the nursing interventions when caring for a client with a chest tube
- Use clinical judgment to prevent, assess, manage, and document complications related to chest tubes

A **chest tube** is a catheter inserted into the pleural space in the chest cavity (also referred to as the thoracic cavity or thorax) to remove air, blood, and/or fluids. Chest tubes are inserted for a variety of reasons, ranging from emergent placement to routine use after cardiopulmonary surgery. Chest tubes are also often used to re-expand collapsed lungs by returning a negative pressure state within the chest cavity. The physiology of negative pressure is discussed in the “Basic Concepts” section of this chapter.

Safe management of patients with chest tube drainage systems requires an active role by the nurse. Nurses must comprehend the principles of

intrathoracic negative pressure, understand the reason a chest tube is indicated for a specific patient, and be knowledgeable of potential problems and/or complications that may occur. This chapter will review the principles of intrathoracic pressure, the indications for chest tubes, and the safe management of patients with chest tube drainage systems.

6.2 Basic Concepts

Review of Anatomy and Physiology

The lungs sit to the left and right of the heart within a space called the thoracic cavity. The cavity is protected by the rib cage. A sheet of muscle called the diaphragm sits at the bottom of the thoracic cavity and separates it from the abdominal cavity. For this reason, the thoracic cavity is a closed space with its own intrathoracic pressure.¹

There are two membranes in the thoracic cavity. The visceral pleura membrane covers the outside of the lungs, and the parietal pleura membrane lines the interior chest wall. The space between these two membranes is called the pleural space (also referred to as the pleural cavity). The **pleural space** normally contains between 10 to 20 mL of pleural fluid that provides lubrication as the pleura continuously slide against each other during inspiration and expiration.² See Figure 6.1³ for an illustration of the pleural cavity (i.e., pleural space).

1. A.D.A.M. Medical Encyclopedia [Internet]. Atlanta (GA): A.D.A.M., Inc.; c1997-2022. Breathing; [updated 2021, February 12]. <https://medlineplus.gov/ency/anatomyvideos/000018.htm#:~:text=The%20second%20phase%20is%20called,and%20air%20is%20forced%20out>
2. Merkle, A. (2022). *Care of a chest tube*. StatPearls. <https://www.statpearls.com/ArticleLibrary/viewarticle/41781>
3. "2313_The_Lung_Pleurea.jpg" by OpenStax College is licensed under [CC BY 3.0](https://creativecommons.org/licenses/by/3.0/)




Figure 6.1 The Pleural Cavity

The process of breathing, known as ventilation, is divided into two distinct phases called inspiration and expiration. During inspiration (also called inhalation), the diaphragm contracts and pulls downward while the intercostal muscles between the ribs pull upward. This movement increases the size of the thoracic cavity, thus decreasing the intrathoracic pressure. This change in pressure on inspiration is referred to as **negative pressure**. As a result, pressure is lower inside the thoracic cavity than atmospheric pressure, creating a vacuum effect that causes air to rush into the lungs on inspiration.⁴

During expiration (also called exhalation), the diaphragm relaxes, and the volume of the thoracic cavity decreases as the chest recoils. As a result, the intrathoracic pressure increases and becomes higher than atmospheric pressure, causing air to be forced out of the lungs.

4. A.D.A.M. Medical Encyclopedia [Internet]. Atlanta (GA): A.D.A.M., Inc.; c1997-2022. Breathing; [updated 2021, February 12]. <https://medlineplus.gov/ency/anatomyvideos/000018.htm#:~:text=The%20second%20phase%20is%20called,and%20air%20is%20forced%20out>



View the following supplementary Medline Plus video⁵ reviewing the physiology of breathing: *Breathing*

Pleural Disorders and Indications for Chest Tubes

An injury, inflammation, or infection can cause blood, fluid, or air to build up in the pleural space. The buildup of air or fluid can put pressure on the lung and cause all or part of it to collapse. Chest pain, shortness of breath, and coughing are common symptoms of pleural disorders, but the treatment for pleural disorders varies depending on the type of disorder and its seriousness. If left untreated, pleural disorders can lead to serious problems, including complete collapse of the lung, shock, or sepsis.⁶

When a lung collapses due to leaked air into the pleural space, it is called a **pneumothorax**, and when it collapses due to blood in the pleural space, it is called a **hemothorax**.⁷ See Figure 6.2⁸ for an illustration of a pneumothorax.

5. A.D.A.M. Inc. (2021, February 2). *Breathing* [Video]. Medline Plus. All rights reserved. <https://medlineplus.gov/ency/anatomyvideos/000018.htm#:~:text=The%20second%20phase%20is%20called,and%20air%20is%20forced%20out>

6. National Heart, Lung, and Blood Institute. (2022, March 24). *What are pleural disorders?* U.S. Department of Health & Human Services. <https://www.nhlbi.nih.gov/health/pleural-disorders>

7. National Heart, Lung, and Blood Institute. (2022, March 24). *What are pleural disorders?* U.S. Department of Health & Human Services. <https://www.nhlbi.nih.gov/health/pleural-disorders>

8. "Blausen_0742_Pneumothorax.png" by Blausen.com staff (2014) at [Medical gallery of Blausen Medical 2014](#) is licensed under [CC BY 3.0](#)




Figure 6.2 Pneumothorax

There are different types of a pneumothorax: spontaneous pneumothorax, traumatic pneumothorax, and tension pneumothorax. A **spontaneous pneumothorax** can happen suddenly without any known cause. It can also be caused by medical conditions that affect the lungs, such as chronic obstructive pulmonary disease (COPD). A **traumatic pneumothorax** is caused by a chest injury, such as a bullet wound that pierces the pleural membranes, causing air to rush into the thoracic cavity.

Tension pneumothorax is a medical emergency caused by large pneumothorax that impacts cardiovascular functioning. The increasing thoracic pressure interferes with blood flow through the inferior vena cava, superior vena cava, and right chambers of the heart, causing the patient's cardiac output and blood pressure to significantly drop. Due to increasing thoracic pressure, a tension pneumothorax causes the patient's trachea to shift to the unaffected side.⁹

9. National Heart, Lung, and Blood Institute. (2022, March 24). *What are pleural disorders?* U.S. Department of Health & Human Services. <https://www.nhlbi.nih.gov/health/pleural-disorders>

Other conditions that may require the placement of a chest tube include the following:

- **Pleural effusion:** Accumulation of fluid in the pleural space, often due to a medical condition such as cancer or heart, kidney, or liver failure
- **Chylothorax:** A collection of lymph in the pleural space
- **Empyema:** A pyogenic infection (pus) of the pleural space
- **Hydrothorax:** Accumulation of serous fluid in the pleural space

Chest tubes are indicated for these pleural disorders to remove air and/or fluid from the pleural space, reestablish negative pressure, and allow the lung to re-expand.

Chest Tube Placement Location

A chest tube is a sterile catheter that is inserted into the pleural space with small drainage holes at the proximal end of the tube to allow for drainage of air or fluid. See Figure 6.3¹⁰ for an image of the proximal end of the chest tube that is inserted into the patient's pleural space.

10. "Chest_Tube_Drainage_Holes.jpg" by Bentplate84 is licensed under [CC BY-SA 3.0](https://creativecommons.org/licenses/by-sa/3.0/)



Figure 6.3 Chest Tube

The distal end of the chest tube is connected to a closed drainage system. See Figure 6.4¹¹ for an image of a closed chest tube drainage system connected to a mannikin. The closed system drains air and fluid from the patient's pleural space and prevents air or fluid from entering the pleural space. It is airtight and helps restore negative pressure in the thoracic cavity.¹² The chest tube drainage system must be maintained in an upright position below the patient's chest to facilitate drainage. It should be placed on a non-movable surface or hung on the bed to prevent accidental dislodgment.

11. "Book-pictures-2015-687-001.jpg" by British Columbia Institute of Technology (BCIT) is licensed under [CC BY 4.0](#). Access for free at <https://opentextbc.ca/clinicalskills/chapter/10-7-chest-drainage-systems/>

12. This work is a derivative of [StatPearls](#) by Ravi & McKnight and is licensed under [CC BY 4.0](#)



Figure 6.4 Closed Chest Tube Drainage System

The location where the chest tube is inserted in the patient's chest is based on the medical condition and the contents that need to be drained from the pleural space. For example, if a patient has a pneumothorax and air needs to be removed from the pleural space, the chest tube is placed higher within the thoracic cavity because air rises. It is typically placed in the second or third intercostal space of the anterior chest. As the air is removed from the patient's pleural space, it disperses into the atmosphere, so there is little or no drainage collecting in the drainage system.¹³

Conversely, if fluid must be removed from the pleural space, it tends to settle in the lower portion of the lung cavity due to gravity. For this reason, chest tubes are often inserted in the lower posterior or lateral chest to drain blood and fluid. Suction is often applied to help promote the removal of the fluid. See Figure 6.5¹⁴ for an illustration of common chest tube placement sites.

13. This work is a derivative of [StatPearls](#) by Ravi & McKnight and is licensed under [CC BY 4.0](#)

14. "Common-insertion-site-of-chest-tube-for-air-and-fluid" by unknown author is licensed under [CC BY-NC-ND 4.0](#). Access for free at https://www.researchgate.net/figure/Common-insertion-site-of-chest-tube-for-air-and-fluid_fig2_279737006




Figure 6.5 Common Chest Tubes Placement Sites

Chest tubes are also routinely placed postoperatively after cardiac surgery to eliminate mediastinal blood. They are typically placed through incisions near the inferior aspect of the sternotomy incision.

Chest Tube Drainage System Chambers

There is a wide range of chest tube drainage system models that have evolved over time with new technology. However, the basic design principles of these systems are the same: to prevent air from entering the pleural cavity during the various phases of the respiratory cycle and to allow for continuous drainage of air and/or fluid from the pleural cavity. To ensure successful and safe treatment of patients with chest tubes, nurses must have a good understanding of the functioning of the specific models of chest tube drainage systems used in their agency.¹⁵ Always follow agency policy and manufacturer's directions for setup, monitoring, and use.

In general, traditional chest tube drainage systems have three chambers¹⁶:

- **Collection chamber:** The chest tube exits the incision from the patient's

15. "Chest Drainage Systems in Use" by Zisis, et al. is licensed under [CC BY-NC-ND 4.0](#)

16. This work is a derivative of [Clinical Procedures for Safer Patient Care](#) by British Columbia Institute of Technology and is licensed under [CC BY 4.0](#)

chest wall and connects directly to the collection chamber to collect drainage from the pleural space. The collection chamber is calibrated so that drainage can be directly measured in the device. The outer surface of the chamber has a surface that can be written on to document the date, time, and amount of fluid collected. This chamber is typically on the far right side of the system.¹⁷

- **Water seal chamber:** The water seal chamber has a one-way valve that allows air to exit the patient’s pleural cavity during exhalation but does not allow it to reenter during inhalation. The water seal chamber is filled with sterile water and maintained at the 2 cm mark to ensure proper operation. This level should be checked regularly and filled with additional sterile water as needed. The water in the water seal chamber may rise with inhalation and fall with exhalation (referred to as **tidaling**). Tidaling indicates the chest tube is patent. However, continuous bubbling in the water seal chamber may indicate an air leak. Some chest drainage systems have a feature that allows for measurements of air leaks. Read more about this feature later in this section.¹⁸
- **Suction control chamber:** Not all patients require suction. If a patient has suction ordered, the amount of suction should be prescribed by the provider. There are two types of suction systems that may be used, referred to as a wet suction system or a dry suction system.
 - A **wet suction system** controls suction by the level of water in the suction control chamber and is typically set at -20 cm for adults. If there is less water in this chamber, there is less suction. There should be gentle bubbling in this chamber because it is directly attached to a suction device. However, excessive bubbling can cause rapid evaporation of the water. See Figure 6.6¹⁹ for an image of a wet suction chest tube drainage system. In this image note the drainage in the collection chamber in the right compartment labeled “D,” the

17. This work is a derivative of [Clinical Procedures for Safer Patient Care](#) by British Columbia Institute of Technology and is licensed under [CC BY 4.0](#)

18. This work is a derivative of [Clinical Procedures for Safer Patient Care](#) by British Columbia Institute of Technology and is licensed under [CC BY 4.0](#)

19. “[Chest drain - bedside with fluids.jpg](#)” by [Johntex](#) is licensed under [CC BY-SA 3.0](#)

water seal chamber in the middle compartment labeled “C,” and -20 cm of water in the suction control chamber in the left compartment labeled “A.”

- A **dry suction system** uses a regulator to adjust the amount of suction and also responds to air leaks to deliver consistent suction for the patient.²⁰ See Figure 6.7²¹ for an image of a dry suction chest tube system. Note the collection chamber on the right, the water seal chamber in the middle, and the dry suction regulator on the left.




Figure 6.6 Wet Suction Chest Tube Drainage System

20. This work is a derivative of [Clinical Procedures for Safer Patient Care](#) by British Columbia Institute of Technology and is licensed under [CC BY 4.0](#)

21. “[Labelled_chest_tube_drainage_system.png](#)” by British Columbia Institute of Technology (BCIT) is licensed under [CC BY-SA 4.0](#)




Figure 6.7 Dry Suction Chest Tube Drainage System

Air Leak Monitor

Chest tube drainage systems may include many safety features. For example, an air leak in the water seal chamber can indicate that air is reentering the patient's pleural space, which can indicate worsening of a pneumothorax. Some chest tube drainage systems contain a feature in the water seal chamber that facilitates the measurement of the degree of an air leak from the chest cavity. See Figure 6.8²² for an image of an air leak meter. The meter is made up of numbered columns, labeled from 1 (low) to 5 (high). The higher

22. "atm-03-03-43-f2.jpg" by Charalambos Zisis, et al. for *Annals of Translational Medicine* is used under Fair Use. Access for free at [10.3978/j.issn.2305-5839.2015.02.09](https://doi.org/10.3978/j.issn.2305-5839.2015.02.09)

the numbered column through which bubbling occurs, the greater the degree of air leak. By documenting the numbered column through which bubbling is occurring, the nurse can monitor the increase or decrease of the air leak.




Figure 6.8 Air Leak Meter in the Water Seal Chamber. Used under Fair Use.

There are many different types and manufacturers of chest tube drainage systems. View a supplementary chest drain education video²³ by Gentinge that demonstrates the various components of their dry suction water seal chest drain: *Express Dry Suction Dry Seal Chest Drain*.

HEIMLICH VALVE

A Heimlich valve is an alternative to a chest tube drainage system. It is a small,

23. Gentinge. (n.d.) *Express dry suction dry seal chest drain* [Video]. Gentinge. All rights reserved. <https://www2.gentinge.com/us/education/chest-drain-education/#>

specially designed flutter valve that is portable and mobile, allowing a patient with a chest tube to ambulate with ease. The valve functions in any position, never needs to be clamped, and can be hooked up to suction if required. It can also be worn under clothing.²⁴ See Figure 6.9²⁵ for an image of a Heimlich valve.



Figure 6.9 Heimlich Valve

The blue end of the Heimlich valve attaches to the chest tube inserted into the patient's chest wall, and the other end can be left open to air or attached to a drainage bag. Air enters the inlet nozzle from the patient's pleural space and opens a rubber sleeve inside the Heimlich valve. The sleeve collapses near the inlet nozzle, preventing the backflow of air into the patient, and then reopens at the outlet nozzle and allows air to escape.²⁶ See Figure 6.10²⁷ for a visual demonstration of how the Heimlich valve works.

24. This work is a derivative of [Clinical Procedures for Safer Patient Care](#) by British Columbia Institute of Technology and is licensed under [CC BY 4.0](#)

25. "Book-pictures-2015-688.jpg" by unknown author is licensed under [CC BY 4.0](#). Access for free at <https://opentextbc.ca/clinicalskills/chapter/10-7-chest-drainage-systems/>

26. This work is a derivative of [Clinical Procedures for Safer Patient Care](#) by British Columbia Institute of Technology and is licensed under [CC BY 4.0](#)

27. "Heimlich_valve.GIF" by [Orinoco-w](#) is licensed under [CC BY-SA 3.0](#)




Figure 6.10 Heimlich Valve

6.3 Nursing Responsibilities for Clients With Chest Tube Drainage Systems

There are several nursing responsibilities related to caring for clients with chest tube drainage systems. Some assessments and interventions should occur at the start of the shift to ensure the client is stable and the chest tube drainage system is functioning appropriately, whereas other interventions and monitoring occur throughout the shift.

Assessments and Interventions at the Start of Shift

- Verify the provider's current orders regarding chest tube setting and care. Note the level of suction prescribed, if ordered, and verify the current wall suction setting.
- Obtain and document baseline vital signs (including oxygen saturation) and perform a focused respiratory assessment, including auscultation of lung sounds, current level of dyspnea, and trachea alignment. Gathering baseline data is important because changes that occur during the shift can indicate a malfunction in the chest tube drainage system and/or a change in patient condition.
- Continually monitor vital signs closely, watching for trends and changes in respiratory rate, oxygen saturation, and blood pressure that could indicate complications are occurring, such as a pneumothorax.
- Obtain a baseline pain assessment, especially regarding the chest tube insertion site. Based on findings, reposition the client, use other nonpharmacological interventions, and/or administer pain medications as prescribed.
- Assess the dressing over the chest tube insertion site to ensure it is dry and intact. Based on agency policy and provider orders, change soiled dressings or reinforce loose dressings.
- Assess the condition of the skin surrounding the insertion site for signs of infection (redness or purulent drainage) or bleeding. Palpate the area surrounding the dressing for **crepitus** (i.e., puffiness or crackling that indicates **subcutaneous emphysema**, the leakage of air into the subcutaneous tissues surrounding the insertion site).

- Assess the chest tube drainage system:
 - Ensure the system is upright and maintained below the client's chest to prevent fluid from flowing back into the client's chest. Some drainage systems have floor stands to prevent the unit from tipping over; if floor stands are present, ensure they are pulled out and perpendicular to the unit. If a stopcock is attached, ensure it is positioned to allow for drainage into the drainage system.
 - Ensure the tubing is not kinked so clots do not form. Any drainage present should be flowing freely into the collection chamber. However, do not "strip" the tubing (i.e., occlude the chest tube with one hand while quickly squeezing and moving the other hand down the tube to move fluid into the drainage chamber). Doing so can cause high intraluminal pressures that can cause a life-threatening pneumothorax.
 - Ensure the system remains closed (i.e., without air leaks) by verifying all tubing connections are taped and the chest tube is securely fastened to the client's chest wall.
 - Assess and document the amount, color, and characteristics of fluid in the collection chamber. Mark the drainage level with the time and date on the outside of the collection chamber for quick future reference during your shift.
 - Ensure the water seal chamber is filled with sterile water to the 2 cm mark (or as specified by the manufacturer). Tidaling should be seen in the water seal chamber. If tidaling is not occurring, the system may not be working properly, the tubing may not be patent, or the client's lung may have re-expanded.
 - There should not be continuous bubbling in the water seal chamber because this may indicate a leak. Immediately try to identify and correct causes of external leaks, such as loose tubing connections. Check the insertion site to ensure the tube has not become dislodged. Immediately notify the health care provider if the tube has become dislodged or you cannot identify or correct an external leak because an air leak can indicate a complication is occurring, such as a worsening pneumothorax.

- If the chest tube drainage system is a wet suction device, ensure the suction control chamber is filled with sterile water to the -20 cm level or as prescribed. There should be constant, gentle bubbling in the suction control chamber if it is connected to suction.
- If the chest tube drainage system is a dry suction device, ensure the rotary dry suction control dial is turned to the ordered suction mark (typically -20 cm water). Refer to the manufacturer's instructions regarding suction indicators. (In some systems, a ball or float appears in an indicator window to indicate the correct amount of suction, whereas other systems have a bellows that reaches a calibrated triangular mark.)
- Verify equipment and supplies are present in the room (in the event a malfunction occurs) according to agency policy and manufacturer recommendations, such as the following:
 - Two sets of rubber-tipped clamps. Chest tubes may be momentarily clamped (according to agency policy) when replacing the chest tube drainage unit, assessing for the location of an air leak, assessing the client's tolerance of chest tube removal, and during chest tube removal. However, routine clamping of the chest tube is not recommended because of the risk of a tension pneumothorax.
 - Sterile 4" x 4" gauze pads and/or petroleum gauze and tape. For example, if air can be heard leaking from the tube insertion site on the client's chest or the chest tube inadvertently becomes dislodged from the client's chest, follow agency policy. Typically, this includes immediately taping a dressing over the insertion site on three sides to allow air to escape and prevent a tension pneumothorax while the provider is notified.
 - Small container of sterile water or saline to use to create a temporary water seal if the tubing becomes disconnected from the drainage system.
- Instruct the client to do the following:
 - Immediately report any breathing difficulty. (Note: Notify the provider immediately if the client develops rapid or shallow breathing, decreased oxygenation saturation level, cyanosis, subcutaneous

emphysema, chest pain, or excessive bleeding.)

- Sit upright to facilitate drainage of fluid and optimal lung expansion.
- Splint the insertion site with a pillow while coughing to minimize pain.
- Perform coughing and deep breathing exercises and/or incentive spirometry, change position, and ambulate as ordered, to facilitate lung expansion and drain fluid from the pleural space.

Monitoring and Interventions Throughout the Shift

- Assess the client's respiratory and pain status every 2 to 4 hours (or according to agency policy). Assess lung sounds, noting decreased or absent lung sounds, which can indicate a worsening pneumothorax or hemothorax and requires immediate notification of the provider. Monitor for new or worsening subcutaneous emphysema and notify the provider if present. Provide pain management according to the client's pain management goals. Obtain emergency assistance for sudden or increased intensity of dyspnea, oxygen saturation less than 90%, or tracheal deviation.
- Monitor for changes in vital signs. If the client develops tachycardia and/or hypotension, a tension pneumothorax could be occurring if there is increased pressure within the thoracic cavity.
- Assess the integrity of the drainage system and tubing every 1 to 4 hours per agency policy. Ensure the system remains intact, the tubing is patent, and there are no air leaks.
- If the chest tube was placed to remove drainage, monitor the amount, color, and consistency of drainage in the drainage tubing and in the collection chamber. Notify the provider if any of the following occur:
 - Drainage appears cloudy because this can be a sign of infection.
 - Drainage stops within the first 24 hours after the chest tube was inserted. This may indicate the tube has become displaced internally or is clotted. (However, be aware of the indication for chest tube placement because in cases addressing a pneumothorax, there may not be any drainage because only air is being removed.)

- Drainage averages more than 200 mL/hour for 4 hours. This may indicate vascular injury that requires surgical repair.¹
- Periodically check that the air vent in the drainage system is working properly (if applicable). Occlusion of the air vent results in a buildup of pressure in the system that could cause the patient to develop a tension pneumothorax.
- If the client requires transport out of the room, do not clamp the tubing. Instead, disconnect the suction connector tubing from the suction source. The system will continue to collect fluid (by gravity) and/or air (by water seal). Portable suction is also available if clients have an air leak and thus cannot tolerate water seal suction or if it is ordered by the provider.
- If a specimen collection is ordered, remove fluid using a sterile needle and syringe from the self-sealing portion of the chest tube drainage tubing (or a needless syringe from the needless site of the drainage tubing after disinfecting the collection site).
- Change the chest tube drainage system if the collection chamber becomes filled with fluid, preventing drainage from overflowing back up the drainage tube.



View a supplementary YouTube video lecture on the nursing management of chest tubes²:



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=179#oembed-1>

1. Merkle, A. (2022). *Care of a chest tube*. StatPearls. <https://www.statpearls.com/ArticleLibrary/viewarticle/41781>

2. RegisteredNurseRN. (2016, August 3). *Chest tubes nursing care management assessment NCLEX review drainage system* [Video]. YouTube. Used with permission. <https://youtu.be/JB-CqWMyrTM>

6.4 Troubleshooting Problems and Complications

Several potential problems and complications can occur when managing a client with a chest tube drainage system. Table 6.4 outlines potential problems and complications, cues to detect a problem is occurring, and associated nursing interventions.

Table 6.4 Potential Problems, Complications, Cues, and Related Interventions^{1,2}

1. *Chest tube and drainage system monitoring and care*. (2022). Lippincott procedures. <http://procedures.lww.com>
2. This work is a derivative of [Clinical Procedures for Safer Patient Care](#) by British Columbia Institute of Technology and is licensed under [CC BY 4.0](#)

Problems/ Complications	Cues and Interventions
Respiratory Distress	<p>This is a priority concern for a patient with a chest tube drainage system and can be caused by a variety of conditions. Signs and symptoms may include oxygen saturation level less than 90%, decreased breath sounds from baseline, asymmetric chest movements, hypotension, tachycardia or bradycardia, subcutaneous emphysema around insertion site or neck, tracheal deviation, or patient complaints of chest pain or increased dyspnea.</p> <ul style="list-style-type: none"> • Ensure the drainage system is intact with no leaks or blockages such as kinks or clamps. • Provide oxygen as indicated. • Immediately notify the provider. An urgent chest X-ray may be ordered to assess for a displaced tube, tension pneumothorax, or other complication. • Obtain emergency assistance as indicated.

Air Leak

An air leak may be indicated by continuous or intermittent bubbling in the water seal chamber or audible air leaking from the patient's chest.

To determine the source of the leak (i.e., the patient, the tubing, or the drainage device), momentarily clamp the chest tube:

- Using rubber-tipped clamps, begin at the dressing site and clamp the drainage tubing momentarily. Look at the water seal chamber. If bubbling stops, the air leak is from the chest tube site or inside the client's thorax. Unclamp the tube, reinforce the dressing, and notify the health care provider immediately.
- If bubbling continues after clamping the tube near the chest wall, gradually move the clamp down the tubing toward the chest drainage system approximately every 10 to 12 inches. Each time the tubing is clamped, observe the water seal chamber. If the bubbling stops, the leak is located in that area of the tubing or the surrounding connections. Replace the tubing or secure the connections. Be sure to release the clamp.
- If bubbling continues despite clamping near the drainage device, the leak is in the drainage system, and it requires replacement.

Dislodged Chest Tube From the Patient	<p>Dislodgement of the chest tube from the insertion site in the patient's chest is an emergent situation, and agency policy must be followed. In general, the following actions may be performed:</p> <ul style="list-style-type: none"> • Call for assistance and ask a colleague to immediately notify the provider and/or obtain supplies while you stay with the patient. • Immediately cover the chest tube insertion site with a sterile occlusive dressing and tape it on three sides, allowing air to escape on the fourth side to reduce the risk of a tension pneumothorax. • If a client develops respiratory distress or a sudden change in vital signs, call the rapid response team. • Prepare for the reinsertion of a chest tube.
Accidental Disconnection of Tubing or the Drainage System Cracks	<p>Call for assistance in replacing the drainage system and notifying the provider. Momentarily clamp the tube close to the insertion site on the patient's chest wall or alternatively place the distal end of the chest tube in a bottle of sterile water.</p>
Bleeding at the Insertion Site	<p>Bleeding may occur after insertion of the chest tube. Apply pressure to the site, reinforce the dressing, and notify the provider.</p>
Subcutaneous Emphysema	<p>Subcutaneous emphysema can indicate a worsening air leak in the chest cavity or a tension pneumothorax as thoracic pressure increases and forces air from the chest cavity out of the tube insertion site and into the tissues. The provider should be notified if subcutaneous emphysema is new or worsening. It may be helpful to mark the area of subcutaneous emphysema to determine if it is extending and worsening.</p>

Drainage Stops	<p>If drainage suddenly stops in the first 24 hours after chest tube insertion, the tubing may be clogged by a blood clot or by a fluid blockage in a dependent loop:</p> <ul style="list-style-type: none"> • Assess the drainage system and the client. • Inspect for kinks and straighten the tubing along its length to its connection with the collection device. • Reposition the client in an upright position. • Ensure the drainage system is below the level of the client's chest. • If interventions are not successful, notify the health care provider.
Sudden Increase in Bright Red Drainage	<p>An increase of bright red drainage of more than 200 mL/hour may indicate vascular injury that requires surgical repair³:</p> <ul style="list-style-type: none"> • Obtain vital signs and assess the client's cardiopulmonary status. • Notify the health care provider and report the amount and color of drainage.
Drainage Unit Tips Over	<ul style="list-style-type: none"> • Position the unit upright. • Immediately check the fluid level in the water seal for correct volume and replace lost fluid. • If all chambers are contaminated with blood, consider replacing the entire unit. • To prevent future tipping, use the attached floor stand that is a part of the drainage unit. If the client is mobile, consider securing the unit to an IV pole.

Overfilled Water Seal or Suction Control Chamber	<ul style="list-style-type: none"> • Press and hold the negative-pressure relief valve at the top of the chest drainage system to vent excess negative pressure in the water seal chamber. Release the valve when the level of the water returns to the 2-cm mark. • To remove excess water from the suction control chamber, insert a syringe and withdraw excess.
Suction Control Chamber Not Bubbling or Bubbling Too Much	<p>The suction control chamber should have gentle bubbling. Vigorous bubbling can indicate wall suction is set too high and can cause faster evaporation, requiring water to be added.</p> <ul style="list-style-type: none"> • Ensure the suction tubing is connected and the suction source is turned on and set to the prescribed suction amount.

6.5 Checklist: Manage a Closed Chest Tube Drainage System

**Disclaimer: Always follow agency policy and manufacturer recommendations*

Checklist: Manage a Closed Chest Tube Drainage System^{1,2}

- Verify the provider's order regarding chest tube care and management.
- Prior to managing a client with a chest tube, review the indication for the chest tube, the location of the chest tube, recent volume of drainage and characteristics of the drainage, the date of previous dressing change, and any previously recorded air leak measurements or presence of subcutaneous emphysema. Chest tube drainage systems are replaced only when the collection chamber is full or the system is contaminated or damaged.
- Review the client's medical record for allergies to antiseptic solutions and latex.
- Gather the appropriate equipment:
 - Vital signs monitoring equipment
 - Stethoscope
 - Pulse oximeter and probe
 - Disinfectant pad
 - Facility-approved disinfectant
 - Marker
- Perform hand hygiene.
- Confirm the client's identity using at least two patient identifiers.
- Provide privacy.
- Explain the procedure to the client (and family members, if present).
- Ensure safety/emergency equipment is always at the client's bedside and with the client during transportation to other departments. Safety equipment should include the following:
 - Two rubber-tipped clamps

1. *Clinical skills: Essentials collection* (1st ed.). (2021). Elsevier.

2. Lippincott procedures. <http://procedures.lww.com>

- Sterile water
- Petroleum-infused gauze
- 4" × 4" sterile dressings
- Occlusive dressing or waterproof tape
- Small container of sterile water or saline
- Alcohol swabs
- Wear appropriate personal protective equipment (PPE) based on the client's medical condition.
- Complete a focused respiratory assessment and pain assessment and analyze vital signs. Place the client in semi-Fowler's position.
- Assess the client. Assessment should be at a minimum of every 15 minutes for the first hour immediately following chest tube insertion. Continue assessing until the client is stable according to agency policy. Increase monitoring if the client's condition worsens.
- Ensure the chest tube drainage system is below the level of the insertion site and upright to prevent backflow of fluid from the tubing into the chest cavity. Ensure the unit is secured to prevent it from being accidentally knocked over.
- Assess the sterile dressing over the chest tube insertion site to ensure it is dry and intact. Inspect and palpate the insertion site for subcutaneous emphysema.
- Assess the chest tube drainage system to ensure the system is intact and to prevent accidental tube removal or disruption of the drainage system. Ensure tubing is not kinked or bent under the client or in the bed rails or compressed by the bed.
- Coil the drainage system tubing and secure it to the edge of the client's bed.
- Avoid creating dependent loops, kinks, or pressure in the tubing.
- Avoid lifting the drainage system above the client's chest.
- Ensure the prescribed suction is set at the correct level.
- If the chest tube is ordered to "water seal" (i.e., suction is not ordered), ensure the suction port is left open to air.
- Check the water seal chamber to ensure the water level is at 2 cm at least once every shift. Add sterile water as necessary.

- Assess the water seal chamber for tidaling with respirations and ensure continuous bubbling is not occurring.
- If an air leak has been previously reported, assess the air leak meter according to the chest tube drainage system's feature. Document the level of air leak, if it is constant or intermittent, or if the air leak occurs at rest or with coughing.
- Write the date, time, and amount of drainage on the outside of the collection chamber at the end of each shift and as indicated. Record the amount and characteristics of the drainage on the fluid input/output flow sheet and chart.
- Observe the integrity of the drainage system tubing and chest tube every 1 to 4 hours according to agency policy and with any change in the client's condition.
- Promote oxygenation by encouraging the client to perform frequent position changes, deep breathing and coughing exercises, incentive spirometry, and ambulation as ordered.
- Discard used supplies, remove gloves, and perform hand hygiene.
- Help the patient into a comfortable position and place personal items, the tray table, and the call light within easy reach. Make sure the patient knows how to use the call light to summon assistance. To ensure the patient's safety, raise the appropriate number of side rails and lower the bed to the lowest position. Ensure the bed is locked.
- Perform hand hygiene.
- Document the procedure, assessments, and interventions.



View a YouTube video³ showing an instructor demonstration of common chest tube systems:

3. Chippewa Valley Technical College. (2023, January 5). *Managing a chest tube system* [Video]. YouTube. Video licensed under CC BY 4.0. <https://youtu.be/dDMzp3yOGjo>



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=192#oembed-1>

Documentation Cues:

- Date and time that chest tube drainage system was initiated
- Type of chest tube drainage system used
- Location and size of chest tube inserted
- Amount of suction applied to the pleural cavity (if applicable)
- Presence or absence of bubbling or fluctuation in the water seal chamber (if applicable)
- Teaching provided to the client and family, understanding of education, and any need for follow-up teaching

6.6 Checklist: Set Up a Chest Tube Drainage System

**Disclaimer: Always follow agency policy and manufacturer recommendations*

Checklist: Set Up a Chest Tube Drainage System^{1,2}

Note: Refer to agency policy and the manufacturer's guidelines before setting up a system.

- Verify the provider's order to determine the type of drainage system to use.
- Gather the necessary equipment and supplies:
 - Single-use, disposable, sterile chest drainage collection unit (water-seal–wet-suction system, water-seal–dry-suction system, or dry-seal–dry-suction system)
 - Sterile water
 - Nonsterile gloves
 - Tape
 - Sterile dressing
 - Optional: commercial securement device, zip tie, suction source with regulator, and suction connection tubing
- Perform hand hygiene.
- Put on clean gloves.
- Maintain a sterile no-touch technique of the drainage system, including the tubing throughout the procedure.
- Remove any protective wrappers and prepare for setup. Stand the system upright. Use the floor or hangers on the unit. Attach the unit to bed frame, keeping the unit below the level of the insertion site of the chest tube.
- Add sterile water or sterile normal saline to the appropriate compartments according to the manufacturer's instructions:
 - **For a Two-chamber System Without Suction:** Add sterile fluid to the

1. *Clinical skills: Essentials collection* (1st ed.). (2021). Elsevier.

2. Lippincott procedures. <http://procedures.lww.com>

water seal chamber to the required indicated level.

- **For a Three-chamber System With Suction:** Add sterile fluid to the water seal chamber, typically to the 2 cm mark. Add sterile fluid to the suction control chamber, typically to the -20 cm mark. Connect the tubing from the suction control chamber to the suction delivery system (wall or portable).
- **For a Dry Suction System:** Fill the water seal chamber with sterile solution, typically to the 2 cm mark. Adjust the suction control dial for the prescribed level of suction, typically between -10 to -40 cm. Connect the tubing from the suction control chamber to the suction delivery system (wall or portable). Do not occlude the suction control chamber when suction is used. On a dry suction system, do not occlude the positive-pressure relief valve because air will escape.
- Secure all tubing connections with tape or zip ties as indicated by agency policy.
- Discard used supplies, remove gloves, and perform hand hygiene.
- Help the patient into a comfortable position and place personal items, the tray table, and the call light within easy reach. Make sure the patient knows how to use the call light to summon assistance. To ensure the patient's safety, raise the appropriate number of side rails and lower the bed to the lowest position. Ensure the bed is locked.
- Perform hand hygiene.
- Document the procedure.

Documentation Cues:

- Date and time that chest tube drainage system was initiated
- Type of chest tube drainage system used
- Location and size of chest tube inserted
- Amount of suction applied to the pleural cavity (if applicable)
- Presence or absence of bubbling or fluctuation in the water seal chamber (if applicable)
- Teaching provided to the client and family, understanding of education, and any need for follow-up teaching

6.7 Assisting With Chest Tube Placement

Nurses may assist a provider with inserting a chest tube. Table 6.7 describes how to apply the nursing process before and after the chest tube is placed.

Table 6.7 Using the Nursing Process When Assisting With Chest Tube Placement

Nursing Process Phase	Nursing Actions
Assessment	<ul style="list-style-type: none"> • Obtain and analyze the client's vital signs and pulse oximetry. • Complete and document a focused respiratory assessment. • Verify client allergies, particularly allergies to latex or any substance applied to the skin. • Review client medications, noting the use of NSAIDs or prescribed anticoagulants, such as aspirin, ibuprofen, or warfarin, that increase the risk for bleeding. • Review any client lab results such as hemoglobin, hematocrit, and INR (if the client is taking warfarin). • Assess the client's knowledge and understanding of the procedure. • Assess the client's need for analgesia and antianxiety medication.
Diagnosis	<ul style="list-style-type: none"> • Determine nursing diagnoses based on the client's condition/needs at this time, such as impaired gas exchange, ineffective breathing pattern, acute pain, or anxiety.

<p>Outcomes Identification/Planning</p>	<p>There are several expected outcomes after the insertion of a chest tube, such as the following:</p> <ul style="list-style-type: none"> • Stable vital signs • Optimal oxygenation status indicated by oxygen saturation level • No chest pain • Baseline levels of alertness and orientation • Reduced level of anxiety, if present • Breath sounds present in all lung lobes with symmetric lung expansion • Unlabored respirations • Chest tube correctly placed • Chest tube drainage system functioning appropriately
<p>Interventions Post-Procedure</p>	<ul style="list-style-type: none"> • The tube will be connected to the chest drainage system and may be connected to suction based on provider orders. • In the trauma setting, notify the provider if initial output is over 1500 mL or there is 200 mL/hour because this may indicate vascular injury that may require surgical repair.¹ • Assess the client's respiratory status post-procedure, including lung sounds, chest expansion, and reported dyspnea. • Monitor vital signs, including oxygen saturation level. • Assess the client's comfort level and compare to baseline. Administer pain medications as indicated. • Confirm accurate placement of the chest tube has been verified by a chest X-ray.² • Inspect the dressing over the chest tube insertion site to ensure it is intact. (The tube is secured to the chest wall according to institutional preference with sutures, tape, or manufactured appliance.³)

Evaluation	<ul style="list-style-type: none">• Evaluate client response with anticipated decreased dyspnea and decreased pain.• Evaluate the client's ability to cough and deep breathe to promote lung expansion.• Evaluate for proper functioning and maintenance of the chest tube drainage system.• Evaluate for evidence of lung re-expansion.
-------------------	---

1. Merkle, A. (2022). *Care of a chest tube*. StatPearls. <https://www.statpearls.com/ArticleLibrary/viewarticle/41781>
2. Merkle, A. (2022). *Care of a chest tube*. StatPearls. <https://www.statpearls.com/ArticleLibrary/viewarticle/41781>
3. Merkle, A. (2022). *Care of a chest tube*. StatPearls. <https://www.statpearls.com/ArticleLibrary/viewarticle/41781>

6.8 Assisting With Chest Tube Removal

The removal of a chest tube is performed by a health care provider such as a physician, physician's assistant, or nurse practitioner.

Indications for chest tube removal include the following¹:

- Improved respiratory status
- Symmetrical rise and fall of the chest
- Bilateral breath sounds
- Decreased chest tube drainage
- Absence of bubbling in the water seal chamber during expiration
- Improved chest X-ray findings

Nursing Responsibilities

The information below summarizes nursing responsibilities before, during, and after the procedure. Expected outcomes after completing the procedure include re-expansion of the lung, client comfort, and healing of the chest tube insertion site without complications, such as infection.

Pre-Removal

- Prepare the client for removal of the chest tube:
 - Assess the need for analgesia.
 - Obtain required medication orders.
 - Instruct the client about the chest tube removal process and inform them that they may have to take a deep breath and hold when it is removed (Valsalva maneuver) to prevent air from reentering the pleural space.
- Assess the client's lungs for re-expansion:
 - Report the most recent chest X-ray results to the health care provider.
 - Examine the trend in the water seal fluctuation over the last 24 hours.

1. Bauman, M., & Handley, C. (2011). Chest-tube care: The more you know, the easier it gets. *American Nurse Today*, 6(9), 27-32. <https://www.myamericannurse.com/chest-tube-care-the-more-you-know-the-easier-it-gets-2/>

- Note if bubbling is present.
 - Confirm decrease in drainage.
- Assess the client's understanding of the chest tube removal process.
 - Do not clamp the tube before the removal.
 - Administer prescribed pain medication 30 minutes before the procedure, if applicable.
 - Identify the client using two patient identifiers as part of the “time out” process as the procedure begins.

During the Procedure

- Assess the client's level of comfort throughout the procedure.
- Perform hand hygiene and apply PPE, including gloves and face shield if needed.
- Assist the client to a seated, supine, or side-lying position (on the side without the chest tube). Apply a protective fluid impermeable pad under the chest tube.
- Provide physical and emotional support to the client during the procedure, especially as the provider removes dressings and sutures.
- After the health care provider removes the chest tube, applies a sterile occlusive dressing, and secures it, assist the client to an upright position supported with pillows.
- Remove equipment and dispose of supplies appropriately.
- Remove gloves and perform hand hygiene.

After the Procedure

- Auscultate lung sounds.
- Inspect and palpate over the area where the tube was inserted to detect any subcutaneous emphysema.
- Evaluate for any signs of respiratory distress immediately after removal and during the first hours after it is removed. Notify the health care provider if respiratory distress occurs.
- Evaluate vital signs, including oxygen saturation, respiratory status, pain

assessment, and level of anxiety.

- Review post-removal chest X-ray and report to the health care provider.
- After removal of a chest tube drainage system, assess the client at a minimum of every 15 minutes for at least an hour, according to agency policy. After the client is stable, monitoring may be less frequent.
- Frequently monitor the chest dressing for drainage. Change the dressing as prescribed, identifying any indications of infection or nonhealing at the insertion site.

6.9 Documentation

Documentation Tips:

Documentation should include all data described in the pre, during, and post-chest tube removal areas. Record the date/time of the chest tube removal, any drainage not recorded in the collection chamber, and the appearance of the dressing and wound if possible. Note the patient's response to the procedure. Include vital signs and respiratory assessment. Document patient teaching and patient's level of understanding.

Sample Documentation:

06/27/20xx 1430

Chest tube to right lateral lower chest wall intact. Water seal chest tube drainage system in upright position and below the level of the client's chest. Tubing is free of kinks and patent. Suction is set at prescribed -20 mmHg. Tidaling present in water seal system. No air leak identified. 50 mL of serosanguineous drainage noted in collection chamber over 8 hours without clots present. Respiratory rate 18 and pulse oximetry reading 96% on room air. Respirations are symmetrical and unlabored. Breath sounds are diminished in the posterior right lower lobe. No adventitious breath sounds or subcutaneous emphysema noted. Trachea is midline. Dressing is dry and intact. Client rates pain at 2/10 and at a tolerable level. Denies sputum. Continue to encourage deep breathing and coughing hourly. Two clamps and a bottle of sterile water are at the bedside.

Hector Ramos, RN

6.10 Learning Activities

Exercises

(Answers to the exercises are located in the Answer Key at the back of the book).

1. A client is recovering from a thoracotomy and has a right pleural chest tube to drainage. Highlight or place an “X” next to the best indicators showing the client’s condition is resolving and ready for chest tube removal.

	Indicators
	Improved respiratory status
	Asymmetrical rise and fall of the chest
	Diminished breath sounds over right lower lobe
	Decreased chest tube drainage
	Absence of bubbling in the water seal chamber during expiration
	Improved chest X-ray findings

2. Managing chest tubes and drainage systems is essential for client safety. Place an “X” next to each nursing action to indicate whether it is likely to be effective in improving the client’s condition being treated with a chest tube or if it is ineffective.

Nursing Action	Effecti ve	Ineffecti ve
Promote oxygenation by encouraging frequent position changes, mobilization, and deep breathing and coughing exercises.		
Coil the drainage system tubing and secure it to the edge of the client's bed.		
Place the drainage system unit on the client's waist during transport.		
Immediately apply pressure to the chest tube insertion site and apply a sterile petroleum gauze dressing if the tube dislodges.		
Perform routine stripping of the chest tube to prevent blood clots from forming.		
Assess the amount, color, and consistency of drainage in the drainage tubing and in the collection chamber at regular intervals.		

3. The nurse is assessing a patient with a chest tube placed two days ago for a pneumothorax. The system is connected to suction. Which of the following findings indicate that there may be a problem with the chest tube drainage unit?

- a. There is sanguineous drainage in the collection chamber.
- b. There is continuous bubbling in the water seal chamber.
- c. There is vigorous bubbling in the suction chamber.
- d. The water level fluctuates in the water seal chamber with respirations.

Case Study #1

Scott, a 70-year-old male, arrived in the ED with increased shortness of breath and left-sided sharp chest pain. Upon arrival, he is hypertensive, tachycardic, tachypneic, and has an O2 sat of 76%. Lung sounds are absent on the left side. Scott's wife Sarah is

concerned. “I’ve never seen him like this. What is going on?” Scott rates his pain 7/10 but has difficulty speaking.

Scott has a history of COPD and a 50-year history of smoking two packs a day; he has had two exacerbations of COPD in the past year. Rapid COVID-19 test is negative.

The following stat orders are given by the ED provider:

- Attach ECG monitoring
- Obtain a portable chest X-ray STAT
- Provide client education about chest tube insertion
- Ensure informed consent for chest tube insertion
- Insert chest tube and chest tube drainage system

1. What client education should be provided regarding the chest tube?

2. What are the maintenance care priorities for care of the chest tube?

3. Are there any specific concerns related to Scott’s need for a chest tube that should be monitored or addressed?

4. What will you consider as you prepare for placement of the chest tube?

5. What is the purpose of the chest tube? What do you hypothesize is Scott’s primary diagnosis?

6. How often should a chest tube be assessed?


7. What cues would indicate further assessment of the chest tube and the client are needed?



An interactive H5P element has been excluded from this version of the text. You can view it online here:

<https://wtcs.pressbooks.pub/nursingadvancedskills/?p=202#h5p-16>



Test your knowledge using a NCLEX Next Generation-style  [question](#). You may reset and resubmit your answers to this question an unlimited number of times.

VI Glossary

Chest tube: A catheter inserted into the pleural space in the chest cavity (also referred to as the thoracic cavity or thorax) to remove air, blood, and/or fluids.

Chylothorax: A collection of lymph in the pleural space.

Crepitus: Puffiness or crackling that indicates subcutaneous emphysema, the leakage of air into the subcutaneous tissues surrounding the insertion site.

Empyema: A pyogenic infection (pus) of the pleural space.

Hemothorax: A collection of blood in the space between the chest wall and the lung (called the pleural cavity).

Hydrothorax: Accumulation of serous fluid in the pleural space

Negative pressure: During inspiration (also called inhalation), the diaphragm contracts and pulls downward, while the intercostal muscles between the ribs pull upward. This movement increases the size of the thoracic cavity, thus decreasing the pressure inside. This change in pressure on inspiration is referred to as negative pressure. As a result, a vacuum effect is created and air rushes into the lungs.

Pleural effusion: Accumulation of fluid in the pleural space, often due to a medical condition such as cancer or heart, kidney, or liver failure.

Pleural space: Also referred to as the pleural cavity; the space between the membranes of the chest wall (i.e., visceral pleura membrane) and the lung (i.e., the parietal pleura membrane).

Pneumothorax: A collapsed lung that occurs when air leaks into the space between the lung and chest wall.

Spontaneous pneumothorax: Collapse of a lung that occurs suddenly without any known cause.

Subcutaneous emphysema: Air leakage into the subcutaneous tissues surrounding the chest tube insertion site.

Tension pneumothorax: A medical emergency caused by large pneumothorax that affects cardiovascular functioning.

Tidaling: When water in the water seal chamber rises with inhalation and falls with exhalation.

Traumatic pneumothorax: Lung collapse caused by a chest injury, such as

a bullet wound that pierces the pleural membranes, causing air to rush into the thoracic cavity.

Learning Objectives

- Describe cardiac anatomy and physiology
- Apply leads for electrocardiograms (ECGs) and cardiac monitoring
- Identify basic cardiac rhythms
- Outline nursing interventions in response to the identified cardiac rhythm

Nurses assist with obtaining electrocardiograms (ECGs) and implementing cardiac monitoring to analyze the electrical activity of a client's heart. They must be able to interpret abnormal cardiac rhythms and quickly address them or obtain emergency assistance. This chapter will review the anatomy and physiology of the cardiovascular system and the electrical conduction system and then introduce the skills of obtaining an ECG and interpreting basic electrocardiogram patterns.

7.2 Basic Concepts

Before interpreting cardiac rhythms, it is vital to understand the anatomy and physiology of the heart. Let's begin with a basic review of the cardiovascular system. The heart is a fist-sized organ that pumps blood throughout the body. It is the primary organ of the circulatory system. The heart contains four main chambers made of muscle and powered by electrical impulses. The brain and nervous system direct the heart's function. The electrophysiology of the heart will determine the rate and rhythm. The blood pressure is maintained by the contractility of the heart muscle.¹ See Figure 7.1² for an illustration of the heart.




Figure 7.1 The Heart

The parts of the heart are similar to the parts of a house. Both the heart and a house have the following components³:

1. Cleveland Clinic. (2021, August 26). *Heart*. <https://my.clevelandclinic.org/health/body/21704-heart>
2. "Heart_diagram-en.svg" by ZooFari is licensed under CC BY-SA 3.0
3. Cleveland Clinic. (2021, August 26). *Heart*. <https://my.clevelandclinic.org/health/body/21704-heart>

- Walls
- Chambers (the rooms)
- Valves (the doors)
- Blood vessels (the plumbing)
- Electrical conduction system (the electricity)

Heart walls are muscles that contract (squeeze) and relax to send blood throughout the body. A layer of muscular tissue called the septum divides the heart walls into the left and right sides. Heart walls have three layers:

- **Endocardium:** The inner layer
- **Myocardium:** The muscular middle layer
- **Epicardium:** The protective outer layer

The epicardium is one layer of the pericardium. The **pericardium** is a protective sac that covers the entire heart. It produces fluid to lubricate the heart and keeps it from rubbing against other organs.⁴

The heart is divided into four chambers. There are two chambers on the top (called the left and right atria) and two chambers on the bottom (called the left and right ventricles). Blood flows through the chambers of the heart in the following order:

- **Right atrium:** Two large veins called the superior vena cava and the inferior vena cava deliver oxygen-poor blood to the upper right chamber of the heart called the right atrium. The **superior vena cava** carries deoxygenated blood from the upper body. The **inferior vena cava** carries deoxygenated blood from the lower body. The right atrium pumps this blood through the tricuspid valve into the right ventricle.
- **Right ventricle:** This lower right chamber of the heart pumps the oxygen-poor blood through the pulmonary valves and then through the **pulmonary arteries** to the lungs. (Note that arteries usually carry oxygenated blood, but pulmonary arteries carry deoxygenated blood to

4. Cleveland Clinic. (2021, August 26). *Heart*. <https://my.clevelandclinic.org/health/body/21704-heart>

the lungs.) The lungs reload blood with oxygen while removing carbon dioxide, and the **pulmonary veins** carry oxygenated blood back to the left atrium. (Note that veins usually carry deoxygenated blood, but pulmonary veins are the only veins in an adult that carry oxygenated blood.)

- **Left atrium:** The upper left chamber of the heart receives the oxygenated blood and pumps it through the mitral valve into the left ventricle.
- **Left ventricle:** The lower left chamber of the heart is called the left ventricle. It is slightly larger than the right ventricle because it pumps oxygen-rich blood through the aortic valve to the coronary arteries and out to the rest of the body.⁵ See Figure 7.2⁶ for an illustration of blood flow through the heart.




Figure 7.2 Blood Flow Through the Heart

5. Cleveland Clinic. (2021, August 26). *Heart*. <https://my.clevelandclinic.org/health/body/21704-heart>

6. "Diagram of the human heart.svg" by Wapcaplet, Yaddah is licensed under [CC BY-SA 3.0](https://creativecommons.org/licenses/by-sa/3.0/)

The heart valves are like doors between the four heart chambers that open and close to allow blood to flow through while preventing blood from moving backwards through the heart. The **atrioventricular (AV) valves** open between the atria and the ventricles (i.e., the upper and lower chambers of the heart). There are two AV valves⁷:

- **Tricuspid valve:** The valve between the right atrium and right ventricle
- **Mitral valve:** The valve between the left atrium and left ventricle

Semilunar (SL) valves open when blood flows out of the ventricles. SL valves include the following⁸:

- **Pulmonary valve:** The valve that opens when blood flows from the right ventricle into the pulmonary arteries (then to the lungs)
- **Aortic valve:** The valve that opens when blood flows out of the left ventricle to the aorta

The heart pumps blood through three types of blood vessels called arteries, veins, and capillaries⁹:

- **Arteries** carry oxygen-rich blood from the heart to the body's tissues. (As previously noted, the exception is the pulmonary arteries that carry deoxygenated blood to the lungs.) The **aorta** is a large artery that carries oxygen-rich blood from the heart to the rest of the body. The heart itself receives oxygen and nutrients through a network of **coronary arteries** that run along the heart's surface.
- **Veins** carry oxygen-poor blood back to the heart. (As previously noted, the exception is the pulmonary veins that carry oxygenated blood from the lungs to the heart.)
- **Capillaries** are small blood vessels where the body exchanges oxygen and carbon dioxide in the blood at the cellular level.

7. Cleveland Clinic. (2021, August 26). *Heart*. <https://my.clevelandclinic.org/health/body/21704-heart>

8. Cleveland Clinic. (2021, August 26). *Heart*. <https://my.clevelandclinic.org/health/body/21704-heart>

9. Cleveland Clinic. (2021, August 26). *Heart*. <https://my.clevelandclinic.org/health/body/21704-heart>

View a supplementary YouTube video¹⁰ on the anatomy and physiology of the heart in a virtual reality lab: *Heart Anatomy and Flow by Dr. Nick Slamon*.

The electrical conduction system of the heart is similar to the electrical wiring of a house. The heart has a network of electrical bundles and fibers that control the rhythm and pace of the heartbeat. The electrical conduction system includes these components¹¹:

- **Sinoatrial (SA) node:** The SA node is located in the upper part of the right atrium and is a major element of the conduction system. The SA node is often referred to as the heart's natural pacemaker. The natural pacemaker rate for the SA node is 60-100 beats per minute. It sends the signals that make the heart beat with a normal rate and rhythm.
- **Atrioventricular (AV) node:** The AV node is located in the lower part of the right atrium. The AV node carries electrical signals from the SA node to the ventricles. If the SA node fails to send signals, the AV node takes over. The AV node is the "backup" pacemaker if the SA node fails. The AV node will pace the heart at a rate of 40-60 beats per minute.
- **Bundle of His:** A collection of cardiac cells found along the septum between the ventricles that sends electrical impulses from the AV node to the left and right bundle branches.
- **Left bundle branch:** Offshoots from the bundle of His that send electrical impulses to the left ventricle.
- **Right bundle branch:** Offshoots from the bundle of His that send electrical impulses to the right ventricle.
- **Purkinje fibers:** A network of thin filaments that carry electrical impulses that cause the ventricles to contract and pump blood out of the heart. If

10. Acadicus. (2021, January 21). Heart anatomy and flow by Dr. Nick Slamon [Video]. YouTube. All rights reserved. <https://youtu.be/SE9MFFjJW8A>

11. Cleveland Clinic. (2021, August 26). *Heart*. <https://my.clevelandclinic.org/health/body/21704-heart>

all other “backup” pacemakers in the heart fail, the Purkinje fibers will pace the heart at 20-40 beats per minute. See Figure 7.3¹² for an illustration of the electrical conduction system of the heart.




Figure 7.3 Electrical Conduction System of the Heart

View the following YouTube video¹³ explaining the electrical conduction system of the heart: [Electrical Conduction System of the Heart: Cardiac SA Node, AV Node, Bundle of His](#).

Dysrhythmias

Occasionally, an area of the heart other than the SA node will initiate an

12. “C_M3_37.jpg” by CCCOnline is licensed under CC BY-SA 4.0. Access for free at <https://pressbooks.cconline.org/bio106/chapter/cardiovascular-levels-of-organization/>

13. RegisteredNurseRN. (2015, May 20). *Electrical conduction system of the heart cardiac | SA node, AV node, bundle of His* [Video]. YouTube. All rights reserved. <https://www.youtube.com/watch?v=-X9rYD8zSOg>

impulse that will be followed by a premature contraction. Premature contractions simply mean these impulses happen too soon and may originate from a different place than a regular beat. These premature contractions can happen in the atrium (premature atrial contraction), ventricle (premature ventricular contraction), or AV junction (premature junctional contractions). Such a contraction is known as an ectopic beat, and the premature contraction causes an irregular heart rate and rhythm during that beat. The underlying heart rate and rhythm can be either regular or irregular. An ectopic focus may be stimulated by localized ischemia, exposure to certain drugs, abnormal electrolytes or acid-base balance, hypoxia, elevated stimulation by both sympathetic or parasympathetic divisions of the autonomic nervous system, or several diseases or pathological conditions. Occasional occurrences of dysrhythmias are generally transitory and not life-threatening. However, if the condition becomes a chronic deviation from the normal pattern of impulse conduction and contraction, it is referred to as **dysrhythmia** or **arrhythmia**. Severe arrhythmias can lead to cardiac arrest, which is fatal if not treated within a few minutes.

Electrocardiograms

Electrocardiograms (ECGs) use leads with electrodes attached to the client's body to record the electrical activity of the heart on special graph paper or on a cardiac monitor. These electrodes detect the small electrical changes of cardiac muscle depolarization followed by repolarization during each cardiac cycle (heartbeat).

A paper rhythm strip is at least a 6-second tracing printed out on special graph paper that shows activity from one or two leads. See Figure 7.4¹⁴ for an example of an ECG rhythm strip. When interpreting a paper ECG, the vertical lines indicate voltage of a given waveform. The thin lines, thick lines, and boxes along the horizontal axis represent various amounts of time as the electrical signal is conducted through the heart tissue:

- Thin lines or small box (1 mm intervals): 0.04 seconds

14. "Normal Sinus Rhythm Unlabeled.jpg" by Andrewmeyerson is licensed under [CC BY-SA 3.0](https://creativecommons.org/licenses/by-sa/3.0/)

- Thick lines or big box (5 mm intervals): 0.2 seconds




Figure 7.4 ECG Rhythm Strip

12-Lead ECG

A **12-lead electrocardiogram** is a diagnostic test that uses 12 leads to record information through 12 different perspectives of the heart to display a complete picture of its electrical activity. Electrodes are placed on the surface of the client's chest (i.e., leads V1, V2, V3, V4, V5, and V6), and four are placed bilaterally on their upper and lower extremities (i.e., RA, LA, RL, LL). In this manner, the heart's electrical activity is measured from twelve different angles (referred to as "leads") to capture each moment throughout the cardiac cycle. Accurate placement of leads to obtain a 12-lead ECG is further described in "[Checklist: Obtain a 12-Lead ECG.](#)"

A standard 12-lead ECG report displays a 2.5 second tracing of each of the twelve leads. The tracings are most commonly arranged in a grid of four columns and three rows. The first column is the limb leads (I, II, and III), the second column is the augmented limb leads (aVR, aVL, and aVF), and the last two columns are the precordial leads (V1 to V6). See Figure 7.5¹⁵ for an image of a 12-lead ECG with the various waveforms.

15. "[Sinustachy.JPG](#)" by [James Heilman, MD](#) is licensed under [CC BY-SA 3.0](#)




Figure 7.5 12-Lead ECG

Each of the 12 ECG leads records the electrical activity of the heart from a different angle and, therefore, aligns with different anatomical areas of the heart:

- Inferior leads (II, III, and aVF): Inferior surface of the heart
- Lateral leads (I, aVL, V5, and V6): Lateral wall of the left ventricle
- Septal leads (V1 and V2): Septal surface of the heart
- Anterior leads (V3 and V4): Anterior wall of the right and left ventricles

When administered and interpreted accurately, an ECG can detect and monitor several types of heart conditions such as dysrhythmias, heart attacks (myocardial infarction), and electrolyte imbalances.

Telemetry

Telemetry refers to a portable device used to continuously monitor clients' heart rhythms. While a client is on telemetry (also referred to as cardiac monitoring), their heart's electrical patterns are displayed on a monitor. The patterns are continuously monitored by specially trained technicians and nurses who interpret the heart's electrical activity. Nurses must be able to identify normal and abnormal heart rhythms displayed on a cardiac monitor. Health care agencies provide specialized training to nurses who

work on units with clients on telemetry. See Figure 7.6¹⁶ for an image of a client on telemetry.




Figure 7.6 Telemetry

Artifact

The monitor or ECG strip typically displays the name of the cardiac rhythm the client is experiencing, but this display is not always correct due to artifact. **Artifact** occurs when the electrodes are not making good contact with the skin and/or if the client moves during the tracing. See an image of artifact on an ECG strip in Figure 7.7¹⁷. Artifact may be interpreted by the monitor as ventricular beats or other abnormal cardiac patterns when, in reality, there are no cardiac abnormalities occurring. For this reason, it is important for nurses to observe the client to ensure what is displayed on the monitor is accurate according to the client's condition.

16. "Alex_CM4000.jpg" by Misscurry is licensed under [CC BY-SA 3.0](#)

17. "Sinus Rhythm with Artifact" by Deanna Hoyord is licensed under [CC BY 4.0](#)



Figure 7.7 Artifact

Components of ECG Waveforms

There are five prominent components on an ECG waveform: the P wave; the Q, R, and S components (often referred to as the QRS complex); and the T wave. Each wave represents a specific electrical impulse in the heart with a specific appearance and normal ranges of measurements on the ECG graph paper. See Figure 7.8¹⁸ for an image of these components.




Figure 7.8 Waveforms on an ECG

18. "SinusRhythmLabels.svg" by Agateller (Anthony Atkielski) is licensed in the [Public Domain](#).

The small **P wave** represents the depolarization of the atria. The large **QRS complex** represents the depolarization of the ventricles, which requires a much stronger impulse because of the larger size of the ventricular cardiac muscle. The ventricles begin to contract as the QRS reaches the peak of the R wave, causing a “heartbeat” that is felt when assessing a client’s pulse. Lastly, the **T wave** represents the repolarization of the ventricle.¹⁹

Intervals between waveforms are assessed on an ECG. The **P-P interval** represents the duration between atrial heartbeats. The **R-R interval** represents the duration between the ventricular heartbeats. Both of these intervals should be consistent if the heart rhythm is regular. However, the P-P interval and the R-R interval may not be the same if a client has a dysrhythmia with different atrial and ventricular heart rates. For example, in atrial flutter the atrial rate will be much faster than the ventricular rate.

The **isometric line** (also known as isoelectric line) is used to measure intervals. It is an imaginary line that can be drawn horizontally through the telemetry strip. This is also called the baseline and is used to determine where each component of the heartbeat starts and ends. It also helps to determine if the component has a positive or negative deflection. See Figure 7.9²⁰ for an illustration of the isoelectric line.




Figure 7.9 Isoelectric Line

19. Physical Therapy Reviewer. (n.d.). *How to read an ECG*. <https://ptreviewer.com/electrocardiogram-ecg-2/reading-an-ecg/>

20. “ECG deflection.gif” is a derivative of *Tachycardia_ECG_paper.svg* by Madhero88 and licensed under [CC BY-SA 3.0](https://creativecommons.org/licenses/by-sa/3.0/). Access for free at <http://simple-cardio.blogspot.com/2012/12/ecg-ekg-paper.html>

The **PR interval** is measured from the start of the P wave to the start of the QRS complex. This is where the P wave starts to have a positive deflection off the isometric line to the first negative deflection. The **QRS complex** is measured from the first negative deflection (Q) through the upward spike (R) to the second negative deflection (S) once it returns to the isometric line. The **QT interval** is measured from the first negative deflection (Q) to the end of the T wave or where the T wave returns to the isometric line.

Table 7.2a reviews the characteristics of ECG components and intervals.

Table 7.2a Components and Intervals on an ECG Waveform

	Representation	Duration	Amplitude	Shape	Notes
P wave	Atrial depolarization by the SA node	Less than 0.12 seconds	Less than 2.5 mm	Upward, rounded, and similar appearance	P wave may be inverted or biphasic (i.e., 2 phases) based on the lead being observed, but is typically upward and rounded.
PR interval	Conduction from the atria through the AV node into the ventricles	0.12-0.20 seconds			Can be shortened or lengthened depending on heart rate. Lengthened past 0.2 seconds is referred to as a "heart block" dysrhythmia.

QRS complex	Atrial repolarization and relaxation and ventricular depolarization and contraction	0.06-0.12 seconds	1.0-3.0 mm	<p>Q: Downward deflection</p> <p>R: Upward spike; represents electrical stimulus passing through ventricles on depolarization</p> <p>S: Downward deflection; reflects final depolarization of Purkinje fibers</p>	<p>All 3 waves may not be visible depending on which lead is being observed.</p> <p>A Q wave duration greater than 0.04 seconds, depth greater than 1 mm, or size greater than 25% of the QRS complex amplitude is a sign of a previous myocardial infarction (commonly referred to as a pathological Q wave).</p>
--------------------	---	-------------------	------------	---	--

QT interval	Ventricular depolarization and repolarization	0.36-0.44 seconds			Normal QT interval varies based on gender and heart rate. It may be lengthened (bradycardia) or shortened (tachycardia) depending on heart rate. Corrected QT interval (QTc) is typically monitored because it takes heart rate and gender into consideration. A side effect of many medications is a prolonged QTc interval.
T wave	Ventricular repolarization		Less than 10 mm	Upward, rounded, and similar in appearance; should have a higher amplitude than P wave	Size should be between one eighth and two thirds of the size of the R wave.
ST segment	Isoelectric period when the ventricles are in between depolarization and repolarization	0.005 – 0.150 seconds	Less than 1 mm	Flat, isoelectric section of the ECG between the end of the S wave (often referred to as the J point) and the beginning of the T wave	Depressed ST segments may indicate coronary ischemia; ST elevation may indicate myocardial infarction. ST elevation is typically seen in leads V1 and V2.

7.3 A Systematic Approach to Interpreting an ECG

A systematic approach to interpreting an ECG improves the speed and reliability of the assessment, especially if a dysrhythmia is present. This section outlines a systematic approach to interpreting an ECG, as well as common findings in ECG waveforms that occur during dysrhythmias. Review basic information about ECG waveforms and intervals in Table 7.2a in the “[Basic Concepts](#)” section of this chapter. Supplementary videos demonstrating how to interpret an ECG are provided at the end of this section, and an online cardiac rhythm game in the “[Learning Activities](#)” section provides practice in interpreting ECG strips.

Calculate the Rate

Calculate the ventricular and atrial rates.

There are several methods to calculate the rate. The simplest method to obtain a ventricular rate is to count the number of R waves in a 6-second strip (i.e., over 30 large boxes) and multiply this number by 10. See Figure 7.10¹ for an image of counting the R waves on a 6-second strip for a ventricular heart rate of 80.



Figure 7.10 Calculating the Ventricular Rate by Counting the R Waves in a 6-Second Strip

In a similar manner, the atrial rate can be calculated (if P waves are present) by counting the number of P waves in a 6-second strip and multiplying this number by 10. In order to ensure accuracy of this method, please make sure that the rhythm strip that is used is a 6-second strip.

1. “Counting the R Waves” by [Chippewa Valley Technical College](#) is licensed by [CC BY 4.0](#)

Determine the Regularity of the Rhythm

Determine if the rhythm is regular or irregular.

View leads I, II, aVF, and VI for the most accurate interpretation of the rhythm.² Assess the distances between the R waves to determine the regularity of the rhythm using a caliper or ruler. It is important to assess the distances across the whole strip to account for any potential abnormality. See Figure 7.11³ for an image depicting the R to R distance on an ECG strip. Cardiac rhythms are categorized into four types of rhythms:

- **Regular Rhythm:** The R to R distances are always equal distance apart. For example, normal sinus rhythm is a regular rhythm.
- **Irregularly Irregular Rhythm:** The R to R distances are never equal distances apart. For example, atrial fibrillation is an irregularly irregular rhythm.
- **Regularly Irregular:** The R to R distances are unequal, but there is a repetitive pattern to the unequal distances. For example, second-degree heart block type II may have a regularly irregular rhythm.
- **Occasionally Irregular:** The R to R distances are equal except for an occasional out of place R. For example, sporadic premature ventricular contractions (PVCs) are an occasionally irregular rhythm.



Figure 7.11 Assessing the R to R Distance

2. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

3. "Assessing Distance Between R Waves" by [Chippewa Valley Technical College](#) is licensed by [CC BY 4.0](#)

Assess the P Waves

The P waves are critical to determining the origin of a heartbeat. Assess the following characteristics related to the P waves:

- **Are P waves present?** The absence of P waves indicates the heartbeat did not originate in the SA node.
- **Do all of the P waves look the same?** When a heartbeat originates somewhere other than the SA node, the contour of the P wave changes.
- **Do the P waves occur at a regular rate?** Using a caliper or ruler, assess the distance from “P to P” waves. If this distance varies, there is an issue in conduction from the SA node to the AV node. See Figure 7.12⁴ for an image of assessing the distance between P waves.
- **Is there one P wave with every QRS complex?** This helps to further assess conduction. Is the electrical communication between the atria and the ventricles working correctly?




Figure 7.12 Assessing the P to P Distance

An example of a dysrhythmia that lacks P waves is atrial fibrillation. The presence of “irregularly irregular” narrow QRS complexes with no distinct P waves or a wavy baseline is the hallmark feature in the identification of atrial fibrillation.⁵

4. “Assessing Distance Between P Waves” by [Chippewa Valley Technical College](#) is licensed by [CC BY 4.0](#)

5. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

Determine the PR Interval

Measure the distance from the beginning of the P wave to the beginning of the QRS complex.

Recall that the normal PR interval is 0.12 to 0.2 seconds (i.e., 3-5 small boxes). When the PR interval is too long, there is a problem with conduction from the SA node to the AV node. A delay in SA to AV node conduction is representative of a heart block. See Figure 7.13⁶ for an image of measuring the PR interval.



Figure 7.13 Measuring the PR Interval

The PR interval represents the time from the beginning of atrial depolarization to the start of ventricular depolarization and includes the delay at the AV node. Variations in the PR interval can be seen in various disorders. For example, a long PR interval may indicate first-degree AV block. Short PR intervals are present in conditions with accelerated AV conduction, such as Wolf-Parkinson-White syndrome, a disorder that is present at birth.⁷

Determine the QRS Duration

Measure the distance from the beginning to the end of the QRS complex.

Recall that normal QRS duration is 0.04 to 0.12 seconds (i.e., 1-3 small boxes). When the QRS complex is too wide, it indicates the heartbeat did not originate in the atria. See Figure 7.14⁸ for an image of measuring the QRS duration.

6. "Measuring the PR Interval" by [Chippewa Valley Technical College](#) is licensed by [CC BY 4.0](#)

7. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

8. "Measuring the QRS Duration" by [Chippewa Valley Technical College](#) is licensed by [CC BY 4.0](#)



Figure 7.14 Measuring the QRS Duration

The QRS complex represents ventricular depolarization as the electrical signal passes down from the AV node. A prolonged QRS may indicate hyperkalemia or bundle branch block. A premature ventricular contraction, intraventricular conduction delay (bundle branch block), or other ventricular dysrhythmias are associated with a wide QRS.⁹

Evaluate the T Waves

Evaluate the T waves. Do they follow the QRS complex? Are they upright and rounded?

Recall the T wave represents ventricular repolarization. Its morphology is highly susceptible to cardiac and noncardiac influences such as hormonal and neurological factors. The size of a typical T wave is between one eighth and two thirds of the size of the R wave and a height of less than 10 mm.

Abnormalities in the T wave morphology include inverted, flat, biphasic, or tall tented or peaked T waves. T wave changes can occur with a variety of conditions. Tall T waves in an anterior chest lead III, aVR, and V1 with a negative QRS complex may suggest acute myocardial ischemia. Other causes of T wave abnormalities are caused by temporary physiological factors (for example, after eating a high carbohydrate meal), endocrine or electrolyte imbalances, myocarditis, pericarditis, cardiomyopathy, post-cardiac surgery state, pulmonary embolism, fever, infection, anemia, acid-base disorders,

9. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

drugs, endogenous catecholamines, metabolic changes, acute abdominal processes, and intracranial pathology.¹⁰

Evaluate the ST Segment

What is the appearance of the S-T segment? Is it isoelectric (i.e., is it on the same level of the PR segment)?

Recall the ST segment depicts the interval between the end of ventricular depolarization and the beginning of ventricular repolarization. A normal ST segment falls along the isoelectric line and lies at the same level as the PR interval. See Figure 7.15¹¹ to review an illustration of ST segments, waves, and other intervals discussed in this section.




Figure 7.15 ST Segment and Other Intervals

10. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

11. "ECG-waves-segments-and-intervals-LITFL-ECG-library-3.jpg" by unknown author at [LITFL](#) is licensed under [CC BY-NC-SA 4.0](#). Access the original image at <https://litfl.com/st-segment-ecg-library/>

Elevation or depression of the ST segment by 1 mm or more, measured at the J point, is abnormal. The J point is a region between the QRS complex and the ST segment. ST elevation is highly specific if present in two or more contiguous leads in the setting of an acute myocardial infarction and usually indicates a complete blockage of the coronary artery. If ST elevation on the ECG tracing above the baseline after the J point is at least 1 mm in a limb lead or 2 mm in a precordial lead, it is clinically significant for diagnosing acute myocardial infarction. ST depression greater than 1 mm below the baseline is often a sign of myocardial ischemia or angina. It can appear as a downsloping, upsloping, or a horizontal segment on the ECG. ST depressions are also associated with nonischemic causes, including digoxin toxicity, hypokalemia, hypothermia, and tachycardia.¹²

Determine the QT Interval Duration

Is the QT (or QTc) interval duration within normal limits?

Recall the QT interval, measured from the Q wave to the end of the T wave, represents the start of depolarization to the end of the repolarization of the ventricles. Generally, the normal QT interval is less than 0.4 to 0.44 seconds. Women usually have a slightly longer QT interval than men, and heart rate also impacts the QT interval, so typically the corrected QT interval (QTc) is monitored.

A short QTc (less than 0.36 seconds) may be associated with hypercalcemia, acidosis, hyperkalemia, hyperthermia, or short QT syndrome.¹³ A prolonged QTc presents an imminent risk for serious ventricular arrhythmias, including torsades de pointes, ventricular tachycardia, and ventricular fibrillation. Common causes of QTc prolongation include side effects of medications, electrolyte abnormalities such as hypocalcemia and hypomagnesemia, and congenital long QT syndrome.¹⁴

12. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

13. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

14. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

Evaluate Other ECG Components

Are there extra beats on the waveform? Is anything else abnormal?

The U wave is a small wave that can follow the T wave, though it is not always visible. It represents the delayed repolarization of the papillary muscles or Purkinje fibers and is commonly associated with hypokalemia.¹⁵

The J wave is an abnormal finding typically found during hypothermia. It appears as an extra deflection on an ECG at the QRS complex and ST segment junction.¹⁶

Clinically Observe the Client

When analyzing an ECG strip, it is vital to clinically observe the client for signs and symptoms that determine the significance of the dysrhythmia. For example, the more abnormal a rhythm becomes, the less blood the heart pumps, causing symptoms due to low blood pressure such as dizziness, confusion, and loss of consciousness.¹⁷



View a supplementary YouTube video¹⁸ on ECG interpretation basics:



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=301#oembed-1>

15. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

16. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

17. Physical Therapy Reviewer. (n.d.). *How to read an ECG*. <https://ptreviewer.com/electrocardiogram-ecg-2/reading-an-ecg/>

18. RegisteredNurseRN. (2022, March 7). *EKG/ECG interpretation basics nursing NCLEX | QRS complex, P wave, T wave, PR interval* [Video]. YouTube. All rights reserved. <https://youtu.be/bUF12VIgzPO>



View a supplementary YouTube video¹⁹ on PQRST EKG rhythm:



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=301#oembed-2>

19. RegisteredNurseRN. (2015, May 21). *How to memorize the PQRST EKG rhythm strip wave for anatomy & pathophysiology* [Video]. YouTube. All rights reserved. <https://youtu.be/QAQiK-zRtIQ>

7.4 ECG Patterns and Dysrhythmias

Abnormal ECG waveforms indicate dysrhythmias (also referred to as arrhythmias). Some dysrhythmias can significantly affect the client's clinical status and require rapid nurse response. Early and accurate identification of ECG patterns, assessment of the client's clinical presentation, and knowledge of the agency's policies and procedures regarding treatment will ensure clients receive optimal care.

Recall that the electrical conduction system stimulates the mechanical pumping action of the heart. If the ventricles become unable to effectively pump blood to the rest of the body due to altered electrical signals, signs and symptoms of **decreased cardiac output** occur, such as decreased blood pressure and pulses, prolonged capillary refill, chest pain, shortness of breath, dizziness, confusion, or loss of consciousness. When an ECG demonstrates new abnormal findings, the nurse must immediately assess the client for signs of decreased cardiac output and respond appropriately.

Some dysrhythmias can quickly lead to cardiac arrest, such as ventricular tachycardia, ventricular fibrillation, and third-degree heart block. The nurse must be aware of which rhythms require emergency assistance.

Medical treatments for symptomatic dysrhythmias can include antidysrhythmic medications, cardioversion, defibrillation, and/or implantation of medical devices such as pacemakers and implantable cardioverter defibrillators (ICDs). Cardioversion and defibrillation are further discussed in the "[Cardioversion and Defibrillation](#)" section of this chapter.

ECG patterns are generally classified into three categories depending on whether the signal originates from the SA node (i.e., sinus rhythms), the atria (i.e., atrial rhythms), or the ventricles (i.e., ventricular rhythms). Additionally, heart blocks refer to blocks in the normal pathway of electrical conduction through the heart and can be categorized as sinus node, atrioventricular (AV) node, or bundle branch blocks. The characteristics of each of these types of rhythms and blocks are further discussed in the following sections. A table summarizing the ECG images discussed in this chapter can be found in the "[Appendix of Rhythm Strips](#)."

Sinus Rhythms

Sinus rhythm is a regular rhythm, but the rate varies depending on autonomic nervous system regulation of the sinus node. When the rhythm is regular but there is an abnormal rate, it is called “sinus arrhythmia.” Sinus arrhythmias include sinus tachycardia and sinus bradycardia. Characteristics and treatment of sinus rhythms are summarized in Table 7.4a at the end of this subsection.

Normal sinus rhythm (NSR) originates from the sinus node and describes the characteristic rhythm of a healthy human heart. All components of the ECG waveform are within normal limits. See Figure 7.16¹ for an image of normal sinus rhythm.



Figure 7.16 Normal Sinus Rhythm

A sinus rhythm faster than a normal rate (i.e., greater than 100 in adults) is called a **sinus tachycardia**. Sinus tachycardia is commonly caused by stress, exercise, alcohol, caffeine, and tobacco and can be resolved by addressing these causes. However, sinus tachycardia can also be caused by conditions such as hypovolemia, anemia, fever/infection, decreased oxygenation, cardiac conditions, and some medications, requiring nursing action depending upon the cause. See Figure 7.17² for an image of sinus tachycardia.

1. “Normal Sinus Rhythm” by Deanna Hoyord is licensed under [CC BY 4.0](#)

2. “Sinus Tachycardia.jpg” by Deanna Hoyord is licensed under [CC BY 4.0](#)



Figure 7.17 Sinus Tachycardia

A sinus rhythm with a slower rate than normal range (i.e., less than 60 in an adult) is called a **sinus bradycardia**. Sinus bradycardia may be asymptomatic and normally occur in athletes due to a well-conditioned heart. However, it can also be symptomatic and signify a new cardiac condition or side effect of cardiac medications, requiring nursing action. See Figure 7.18³ for an image of sinus bradycardia.



Figure 7.18 Sinus Bradycardia

Respiratory sinus arrhythmia is typically a normal finding in young, healthy adults where the heart rhythm correlates to the respiratory cycle. As the client breathes in, the heart rate increases and then the rate slows as they breathe out.

Table 7.4a Characteristics of Normal Sinus Rhythm and Common Sinus Dysrhythmias

3. "Sinus Bradycardia" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

Sinus Rhythms	Patho-physiology	Causes	Identification	Symptoms	Nursing Interventions	Medical Treatment	Patient Education
Normal Sinus Rhythm (NSR)	Normal conduction of the heart.	N/A	All components are within normal limits.	N/A	N/A	N/A	N/A
Sinus Bradycardia⁴	Slowed electrical conduction in the heart.	May occur in well-conditioned athletes. Can also signify a cardiac condition or side effects of cardiac medications requiring nursing action.	All components are within normal limits except the heart rate is less than 60 beats per minute.	Many clients are asymptomatic, but if signs and symptoms occur, they are related to decreased cardiac output.	Assess for adequate cardiac output. Withhold cardiac medications if indicated and notify the provider.	If symptomatic, the cause is treated. Atropine, transcutaneous pacemaker, and placement of a permanent pacemaker may be required for chronic bradycardia.	Seek medical care for symptoms such as chest pain, shortness of breath, dizziness, confusion, or fainting.
Sinus Tachycardia⁵	Fast electrical conduction through the heart, causing lack of filling between each beat.	Often caused by stress, exercise, alcohol, caffeine, and tobacco. Can also be caused by hypovolemia, anemia, fever/infection, decreased oxygenation, cardiac conditions, and some medications.	All components are within normal limits except the heart rate is above 100 beats per minute.	Some clients are asymptomatic. Other clients have palpitations or symptoms of decreased cardiac output.	Assess for adequate cardiac output and notify the provider if indicated. Educate about lifestyle changes that could cause the rhythm.	If symptomatic, the underlying cause is treated. Beta-blockers, calcium channel blockers, or sinus ablation may be used to slow the rate.	Eliminate the cause of the rhythm. Seek medical treatment for symptoms of chest pain, shortness of breath, dizziness, confusion, or loss of consciousness.
Respiratory Sinus Arrhythmia⁶	Rhythm correlates to the respiratory cycle; the rate increases when the client breathes in and slows when they breathe out.	Very common in young healthy adults.	All components are within normal limits except the rhythm is irregular and corresponds to the respiratory cycle. If the client holds their breath, the rhythm reverts to NSR.	Rare.	Notify the provider if symptomatic.	Typically, no treatment is needed.	This is a sign of a normal functioning heart.

4. Cleveland Clinic. (2022, March 7). *Sinus bradycardia*. <https://my.clevelandclinic.org/health/diseases/22473-sinus-bradycardia>

5. Cleveland Clinic. (2022, October 3). *Tachycardia*. <https://my.clevelandclinic.org/health/diseases/22108-tachycardia>

6. Cleveland Clinic. (2022, March 21). *Sinus arrhythmia*. <http://my.clevelandclinic.org/health/diseases/21666-sinus-arrhythmia>

Atrial Rhythms

Atrial rhythms originate in the atria rather than in the SA node. The P wave is positive, but its shape can be different from a normal sinus rhythm because the electrical impulse follows a different path to the AV (atrioventricular) node. Common atrial arrhythmias include premature atrial contractions, atrial fibrillation, and atrial flutter. Characteristics and treatment of common atrial dysrhythmias are summarized in Table 7.4b at the end of this subsection.

Premature atrial contractions (PAC) are common in older adults and are caused by ectopic beats that originate in the atria. They are not typically treated unless the client becomes symptomatic.

Atrial fibrillation (A-fib) is categorized as an “irregularly irregular rhythm.” It is characterized by atrial quivering, resulting in a lack of P waves. Clients may develop signs and symptoms of decreased cardiac output because the ventricles are not able to fill and pump the appropriate amount of blood with each beat. Nurses should assess for signs of decreased cardiac output, including fatigue, dizziness, syncope, chest pain, and shortness of breath, as well as for new signs of stroke. Clients with A-fib are at risk of stroke due to blood pooling in the atria. See Figure 7.19⁷ for an image of atrial fibrillation.



Figure 7.19 Atrial Fibrillation

Atrial flutter (A flutter) displays the atrial beats as sawtooth beats, and the PR interval is not measurable. Atrial impulses are fast and regular, with rates between 250-300, and the ventricular rate is not the same as the atrial rate. As a result, the client’s cardiac output decreases because the heart is not able to

7. “Atrial Fibrillation” by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

fill and pump the appropriate amount of blood with each beat. Clients with atrial flutter are also at risk for stroke. See Figure 7.20⁸ for an image of atrial flutter.



Figure 7.20 Atrial Flutter

Table 7.4b Characteristics of Common Atrial Dysrhythmias

8. "Atrial Flutter" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

Atrial Rhythms	Pathophysiology	Causes	Identification	Symptoms	Nursing Interventions	Treatment	Patient Education
Premature Atrial Contractions (PAC) ⁹	An ectopic beat that originates in the atria.	Common in older adults; often caused by caffeine, tobacco, anxiety, and electrolyte imbalances.	Early P waves that may be closer than normal to the previous T wave.	Feelings of a skipped beat or palpitations.	Encourage lifestyle changes, such as decreased caffeine, tobacco, and alcohol intake, as well as improved stress management.	If symptomatic, then treatments are prescribed to eliminate the cause.	Seek medical treatment for symptoms of chest pain, shortness of breath, dizziness, confusion, or fainting.
Atrial Fibrillation (A-fib) ¹⁰	An irregular heart rhythm originating in the atria characterized by atrial quivering. This rhythm is categorized as an “irregularly irregular rhythm.” Clients are at increased risk for a stroke due to blood pooling in the atria.	Coronary artery disease, heart failure, high blood pressure, and cardiac irritability due to ischemia or electrolyte imbalances.	Irregular heart rate with lack of clear P waves and a wavy baseline because they are quivering. PR interval is not measurable.	Irregular heartbeat and possible palpitations. May have signs and symptoms of decreased cardiac output, including fatigue, dizziness, syncope, chest pain, and shortness of breath.	Be aware that atrial and ventricular rates are different and may affect the accuracy of blood pressure readings on automatic monitors. Immediately report signs of decreased cardiac output or signs of stroke.	Medications for stable A-fib include those to control rate and/or rhythm, as well as anticoagulation to prevent strokes. Treatments of unstable A-fib include cardioversion and/or ablation. A pacemaker may be implanted if bradycardia is present.	Seek medical care for symptoms of a stroke, such as one-sided weakness or paralysis, slurred speech, or facial drooping. Seek medical treatment for chest pain, shortness of breath, dizziness, confusion, or fainting.
Atrial Flutter (A flutter) ¹¹	Fast, regular atrial impulses with rates between 250-300. As a result, the heart is not able to fill and pump the appropriate amount of blood with each beat. Clients are at increased risk for stroke.	Coronary artery disease, hypertension, obesity, and heart failure.	Atrial beats appear as sawtooth beats. PR interval is not measurable. QRS may be regular or irregular.	Shortness of breath, syncope, palpitations, and dizziness.	Be aware atrial and ventricular rates will be different. Monitor for signs of decreased cardiac output and stroke.	If stable, medications are prescribed for rate and/or rhythm control, as well as for anticoagulation to prevent strokes. If unstable, cardioversion, ablation, and/or a pacemaker may be performed.	Seek medical care for symptoms of a stroke, such as one-sided weakness or paralysis, slurred speech, or facial drooping. Seek medical treatment for chest pain, shortness of breath, dizziness, confusion, or fainting.

9. Cleveland Clinic. (2021, July 27). *Premature atrial contractions*. <https://my.clevelandclinic.org/health/diseases/21700-premature-atrial-contractions>

10. Cleveland Clinic. (2022, May 1). *Atrial fibrillation (Afib)*. <https://my.clevelandclinic.org/health/diseases/16765-atrial-fibrillation-afib>

11. Cleveland Clinic. (2022, September 21). *Atrial flutter*. <https://my.clevelandclinic.org/health/diseases/22885-atrial-flutter>

Ventricular Rhythms

Ventricular rhythms originate in the ventricles (rather than the SA node) and typically cause the heart to beat faster (i.e., ventricular tachycardia) or quiver (i.e., ventricular fibrillation). There are several different types of ventricular dysrhythmias. Many ventricular dysrhythmias are life-threatening and require immediate emergency response. Common ventricular dysrhythmias include premature ventricular tachycardia (PVC), supraventricular tachycardia, torsades de pointes, ventricular tachycardia (V-tach), and ventricular fibrillation (V-fib). Characteristics and treatment of common ventricular dysrhythmias are summarized in Table 7.4c at the end of this subsection.

Some ventricular dysrhythmias may be unifocal or multifocal. **Unifocal** dysrhythmias causes the waveforms to look the same because the signal is originating from the same area in the heart, whereas **multifocal** dysrhythmias cause the waveforms to look different because the impulse is originating from different areas of the heart. Multifocal rhythms are harder to treat and are more dangerous because the impulse is not predictable and multiple areas of the heart are involved.

Premature ventricular contractions (PVC) are caused by ectopic beats that originate in the ventricle, resulting in the appearance of wide, bizarre QRS complexes within an otherwise normal sinus rhythm. Although occasional PVCs are common in healthy adults with no symptoms other than occasional palpitations, increased frequency of PVCs per minute can signal a more serious condition. **Bigeminy** is a PVC every other beat. **Trigeminy** is a PVC every third beat. **Couplets** refer to PVCs occurring in pairs. See Figure 7.21¹² for an image of unifocal PVCs in an otherwise normal sinus rhythm. See Figure 7.22¹³ for an image of PVCs occurring in couplets.

R on T phenomenon occurs when a PVC occurs on a T wave and can trigger ventricular tachycardia. Medications or diseases that cause prolonged QT interval can result in R on T phenomenon.

12. "Sinus Rhythm with Unifocal PVCs" by Deanna Hoyord is licensed under [CC BY 4.0](#)

13. "Bigeminy PVCs" by Deanna Hoyord is licensed under [CC BY 4.0](#)




Figure 7.21 Sinus Rhythm With Unifocal PVCs



Figure 7.22 Premature Ventricular Contractions (PVCs) – Couplets

Supraventricular tachycardia (SVT) is characterized by a narrow QRS interval of 0.1 second or less and rapid heart rates over 160 beats per minute. P waves often cannot be identified due to fast rate, and cardiac output may decrease due to the inability of the ventricles to fill and pump blood. See Figure 7.23¹⁴ for an image of supraventricular tachycardia.

14. "Supraventricular Tachycardia" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)




Figure 7.23 Supraventricular Tachycardia

Ventricular tachycardia (V-tach) is characterized by wide QRS complexes without visible P and T waves. The ventricular rate is often over 120 beats per minute, resulting in rapidly worsening cardiac output. The client is only able to tolerate this rapid ventricular rhythm for a short period of time before losing consciousness. V-tach requires emergency response. If the client has a pulse, synchronized cardioversion and/or intravenous antidysrhythmic medications are administered. If the client does not have a pulse, defibrillation is administered. Read details about synchronized cardioversion and defibrillation in the “[Cardioversion and Defibrillation](#)” section of this chapter. Read more information about antidysrhythmic medications in the “[Antiarrhythmics](#)” section of the “Cardiac and Renal” chapter of *Open RN Nursing Pharmacology*. See Figure 7.24¹⁵ for an image of ventricular tachycardia.




Figure 7.24 Ventricular Tachycardia

15. “[Ventricular Tachycardia](#)” by Deanna Hoyord is licensed under [CC BY 4.0](#)

Torsades de pointes is a type of V-tach that occurs when there is a long QT interval, and a beat occurs during the QT interval. It resembles ventricular tachycardia but has a pattern of twisting points or peaks. This rhythm can rapidly develop into ventricular fibrillation and requires emergency response. See Figure 7.25¹⁶ for an image of torsades de pointes.



Figure 7.25 Torsades de Pointes

Ventricular fibrillation is characterized by quivering ventricles with no patterns to the waveforms, so nothing can be measured on the ECG. As a result, there are no effective contractions and no cardiac output. This is the most dangerous arrhythmia because of lack of cardiac output and requires immediate initiation of CPR and emergency response. Defibrillation is administered, along with IV antidysrhythmic medications. Read details about defibrillation in the “[Cardioversion and Defibrillation](#)” section of this chapter. Read more information about antidysrhythmic medications in the “[Antiarrhythmics](#)” section of the “Cardiac and Renal” chapter of *Open RN Nursing Pharmacology 2e*. See Figure 7.26¹⁷ for an image of ventricular fibrillation.

16. “Torsades de Pointes” by Deanna Hoyord is licensed under [CC BY 4.0](#)

17. “Ventricular Fibrillation” by Deanna Hoyord is licensed under [CC BY 4.0](#)




Figure 7.26 Ventricular Fibrillation

Some dysrhythmias, such as asystole and pulseless electrical activity, have no electrical conduction through the ventricles, resulting in no contractions and no pulse.

In **asystole** there are no electrical impulses, and a flat line appears on the ECG. CPR and emergency treatment are instituted, but asystole is not a shockable rhythm because there are no existing electrical impulses. See Figure 7.27¹⁸ for an image of asystole.




Figure 7.27 Asystole

Pulseless electrical activity (PEA) is similar to asystole because although electrical activity appears on the ECG, it is not strong enough to stimulate a ventricular contraction or a pulse. CPR and emergency treatment are initiated, but PEA is not a shockable rhythm.

Table 7.4c Characteristics of Common Ventricular Dysrhythmias, Asystole, and PEA

18. "Asystole" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

Ventricular Rhythms	Pathophysiology	Causes	Identification	Symptoms	Nursing Interventions	Treatment	Patient Education
Premature Ventricular Contraction (PVC) ¹⁹	Ectopic beats that originate in the ventricle. Common in healthy adults with no symptoms other than occasional palpitation.	Heart failure, high blood pressure, electrolyte imbalance, stress, alcohol, and excessive caffeine or energy drink consumption.	Wide bizarre QRS complexes within a normal underlying rhythm. May be single or multiple PVCs.	Palpitations and signs of decreased cardiac output depending on how frequent they are occurring.	Monitor for signs of decreased cardiac output.	If PVCs are infrequent or asymptomatic, no treatment is needed. Treatment for symptomatic PVCs include correcting the underlying cause and may include ablation and antiarrhythmic medication.	Educate about potential causes and lifestyle changes such as decreased caffeine and alcohol and improved stress management. Seek medical care for signs of decreased cardiac output.
Supraventricular Tachycardia (SVT) ²⁰	The impulse to the ventricle is fast with ventricular rates often over 160 beats per minute.	Stress, caffeine, alcohol, infection, or sepsis.	Narrow-complex tachycardias with a QRS interval of 0.1 second or less. P waves cannot be identified due to the fast ventricular rate.	Chest pain, fast heartbeat, palpitations, shortness of breath, and syncope.	Prepare to administer medications to slow the heart rate.	Valsalva maneuvers and medications are used to slow the heart rate.	Seek medical care when the heart feels like it is racing or for symptoms of chest pain, shortness of breath, dizziness, confusion, or fainting.
Ventricular Tachycardia (V-tach) ²¹	Ventricular rate over 120 beats per minute, causing rapidly worsening cardiac output.	Coronary artery disease, heart failure, myocarditis, heart surgery, previous damage to the heart, recreational drugs, alcohol, medications, and electrolyte imbalances.	Wide QRS complexes are the only components that are measurable. P and T waves are not visible.	Chest pain, shortness of breath, syncope, palpitations, and cardiac arrest. Client can only tolerate this rhythm for a short period of time before losing consciousness.	Notify the provider and obtain emergency assistance. Prepare to administer IV antidysrhythmic medications, cardioversion, or defibrillation.	Reversible causes are treated. If the client is stable, synchronized cardioversion and IV antidysrhythmic medications are administered. If the client is unstable, defibrillation and CPR are administered, along with IV antidysrhythmic medications.	Call 911 for chest pain, shortness of breath, or fainting.

19. Cleveland Clinic. (2022, July 29). *Premature ventricular contractions*. <https://my.clevelandclinic.org/health/diseases/17381-premature-ventricular-contractions>

20. Cleveland Clinic. (2021, December 1). *SVT (supraventricular tachycardia)*. <https://my.clevelandclinic.org/health/diseases/22152-svt-supraventricular-tachycardia>

21. Cleveland Clinic. (2022, June 12). *Ventricular tachycardia*. <https://my.clevelandclinic.org/health/diseases/17616-ventricular-tachycardia>

Torsades de Pointes ²²	A type of V-tach.	Long QT interval syndrome, certain congenital syndromes, and medications that can prolong the QT interval.	Resembles ventricular tachycardia but looks like twisting points or peaks. Review the first beat to determine if it started in the QT interval.	Chest pain, shortness of breath, syncope, palpitations, and cardiac arrest. Client can only tolerate this rhythm for a short period of time before losing consciousness.	Notify the provider and obtain emergency assistance. Be aware if the client is taking medications that prolong the QT interval. Prepare to administer IV antidysrhythmic medications, cardioversion, or defibrillation.	Reversible causes are treated. Synchronized cardioversion, IV magnesium, and/or IV antiarrhythmic medications are administered. An implantable cardiac defibrillator may be required.	Seek medical care for feelings of the heart racing or palpitations.
Ventricular Fibrillation (V-fib) ²³	The ventricles are quivering with no effective contractions and no cardiac output. This is the most dangerous arrhythmia.	Heart disease, heart attack, heart surgery, untreated arrhythmias, electrolyte imbalances, and electrical shock.	Nothing can be measured because there is just a fibrillatory line. Can be coarse or fine fibrillatory waves. Coarse waves are taller than fine. Fine V-fib is harder to treat and convert to a sustaining rhythm.	Pulselessness and loss of consciousness.	Obtain emergency assistance and initiate CPR. Prepare to administer IV antidysrhythmic medications and defibrillation.	Reversible causes are treated. Defibrillation and IV antiarrhythmic medications administered according to ACLS algorithm.	Not applicable because the client is unconscious.
Asystole ²⁴	There are no electrical impulses occurring in the heart.	Shock, heart attack, untreated arrhythmia, trauma, and toxins.	A flat line appears on the ECG. There is no impulse occurring, so nothing is measurable.	Client is unconscious and does not have a pulse.	Initiate CPR and obtain emergency assistance. Be aware asystole is not a shockable rhythm.	CPR and IV epinephrine are administered, and the underlying cause is treated.	Not applicable because the client is unconscious.
Pulseless Electrical Activity (PEA) ²⁵	There is electrical activity, but it is not strong enough to cause a contraction or a pulse.	Cardiac arrest, shock, untreated dysrhythmias, hypothermia, and trauma.	ECG components may be present, but the client does not have a pulse.	Client is unconscious and does not have a pulse.	Initiate CPR and obtain emergency assistance. Be aware PEA is not a shockable rhythm.	PEA is not a shockable rhythm. CPR and IV epinephrine are administered, and the underlying cause is treated.	Not applicable because the client is unconscious.

22. Cleveland Clinic. (2021, August 13). *Torsades de pointes*. <https://my.clevelandclinic.org/health/diseases/21915-torsades-de-pointes>

23. Cleveland Clinic. (2021, September 20). *Ventricular fibrillation*. <https://my.clevelandclinic.org/health/diseases/21878-ventricular-fibrillation>

24. Cleveland Clinic. (2022, May 3). *Asystole*. <https://my.clevelandclinic.org/health/symptoms/22920-asystole>

25. Cleveland Clinic. (2022, June 3). *Pulseless electrical activity*. <https://my.clevelandclinic.org/health/symptoms/23213-pulseless-electrical-activity>

Heart Block

A **heart block** is an obstruction in the normal pathway of electrical conduction through the heart that can occur in many anatomical locations. The anatomical location of a heart block can be categorized as in the sinus node, atrioventricular (A/V) node, or bundle branches.²⁶

Sinus node blocks (also referred to as sinoatrial exit blocks) occur due to failed conduction of the impulses beyond the SA node, resulting in prolonged PR intervals or dropped P waves on the ECG. Common causes of sinus node blocks include sick sinus syndrome, increased vagal tone, inferior wall MI, vagal stimulation, myocarditis, and drugs (including digoxin and beta-blockers).²⁷

Atrioventricular (AV) blocks are conduction blocks that can occur anywhere between the SA node and Purkinje fibers. There are three variants of AV blocks: first-degree, second-degree, and third-degree. Diagnosing AV blocks requires careful measuring of the PR interval and examining the relationship of the P waves to QRS complexes.²⁸ Certain medications, such as beta-blockers, can contribute to or worsen AV blocks and may need adjustments per the health care provider. First-degree, second-degree, third-degree, and bundle branch blocks are further described in the following subsections. Characteristics and treatments of common heart blocks are summarized in Table 7.4d at the end of this section.

First-Degree Heart Block

First-degree AV block is defined as a prolonged PR interval more than 0.2 seconds. A single P wave precedes every QRS complex by a consistent length. It may be a normal finding in some individuals. Conversely, it can be an early sign of degenerative disease of the conduction system or a transient manifestation of myocarditis, drug toxicity, hypokalemia, and acute rheumatic

26. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

27. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

28. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

fever. It usually does not require any treatment.²⁹ See Figure 7.28³⁰ for an image of first-degree heart block.




Figure 7.28 First-Degree Heart Block

Second-Degree Heart Block

There are two types of second-degree heart blocks: Type I and Type II.

TYPE I

Second-degree Type I AV block is also known as Wenckebach block. The block across the AV node or bundle of His is variable and increases with each ensuing impulse, ultimately resulting in a drop of the impulse. On an ECG, it shows a progressive prolongation of the PR interval, and then suddenly, a P wave is not followed by the QRS complex. This sequence regularly repeats itself. Most clients with Mobitz Type I second-degree AV block are asymptomatic. Mobitz Type I AV block may occur in the setting of acute myocardial ischemia or myocarditis. It may also result in clinical deterioration if the resulting ventricular rate is inadequate to maintain cardiac output. Most clients with Mobitz Type I second-degree AV block are asymptomatic and do not require specific intervention. Occasionally, clients with Mobitz Type I block are symptomatic, demonstrate hemodynamic instability, and require treatment with either atropine or cardiac pacing.³¹

29. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

30. "1st Degree Heart Block" by Deanna Hoyord is licensed under [CC BY 4.0](#)

31. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

TYPE II

Second-degree Type 2 AV block has a consistent PR interval and the duration may be normal, but there are dropped ventricular beats, or QRS complexes, periodically. There can be one or more dropped QRS complexes, which can result in several P waves in a row without QRS complexes following them. This is significant because when ventricular beats are dropped, there is no ventricular output, meaning there is no cardiac output for the preceding P waves. It usually occurs below the AV node at the level of the bundle of His. It clinically signifies a severe underlying heart disease that can progress to third-degree heart block. When diagnosed, it usually requires prompt treatment with a permanent pacemaker.³² See Figure 7.29³³ for an image of second-degree heart block, Type II.



Figure 7.29 Second-Degree Heart Block Type II

Third-Degree Heart Block

Third-degree AV block, also called complete heart block, is characterized by a complete electrical dissociation between the atria and ventricles, resulting in the atria and the ventricles beating at their intrinsic rates irrespective of how the other is beating. Degenerative disease of the conduction system is the leading cause of third-degree heart block. A complete heart block may present in acute myocardial infarction. Complete heart block may be reversible with prompt revascularization, especially in inferior myocardial

32. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

33. "[2nd Degree Type II AV Block.jpg](#)" by Deanna Hoyord is licensed under [CC BY 4.0](#)

infarction. Elevated magnesium levels can also cause third-degree heart block. Lyme disease may be associated with a complete heart block and is potentially reversible with antibiotic therapy. In the case of irreversible or permanent complete heart block, a permanent pacemaker remains the standard treatment.³⁴ See Figure 7.30³⁵ for an image of third-degree heart block.



Figure 7.30 Third-Degree Heart Block

Bundle Branch Blocks

Bundle branch blocks (i.e., intraventricular conduction delays) result from the conduction block of either left or right bundle branches and occur within the ventricles. They are diagnosed by examining the width and configuration of the QRS complexes.³⁶ A generic bundle branch block is characterized by a widened QRS complex greater than 0.12 mm. To determine if it is a right or left bundle branch block, additional 12-lead EKG interpretation is necessary and is beyond the scope of this text.

Table 7.4d Characteristics of Common AV Blocks

34. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

35. "Third Degree Heart Block.jpg" by Deanna Hoyord is licensed under [CC BY 4.0](#)

36. This work is a derivative of [StatPearls](#) by Sattar and Chhabra and is licensed under [CC BY 4.0](#)

AV Blocks	Pathophysiology	Causes	Identification	Symptoms	Nursing Interventions	Treatment	Patient Education
1st-Degree AV Block	There is a slowed impulse from the AV node to the ventricles.	Heart attack, heart muscle disease, heart surgery, medications, toxins, and genetics.	The PR interval is greater than 0.20 seconds and consistent. There is one P wave for each QRS.	Typically, no symptoms.	Typically, none because asymptomatic.	Reverse underlying causes.	This is the least dangerous form of a heart block, but there is a chance it could progress to worse types of heart blocks.
2nd-Degree Type 1 AV Block	The impulse from the AV node to the ventricles gets slower and slower with each beat until there is a dropped beat. The pattern then repeats itself.	Same as 1st-degree block.	The PR interval will become more prolonged with each beat until there is a missing beat.	Syncope, chest pain, shortness of breath, palpitations, shortness of breath, and nausea.	Treat the cause of the block if it is reversible. Monitor for signs of worsening decreased cardiac output.	Reverse underlying causes. If symptomatic, medications prescribed to improve cardiac output until a permanent pacemaker can be placed.	Be aware this type of block can progress to worsening blocks. Seek medical treatment for chest pain, shortness of breath, dizziness, confusion, or fainting.
2nd-Degree Type 2 AV Block	The impulse from the AV node to the ventricles is variable. Some beats will be normal, and other beats will be dropped.	Same as 1st-degree block.	PR interval is consistent. It may be normal or prolonged until the QRS is dropped, resulting in only P waves for those heartbeats.	Syncope, chest pain, shortness of breath, palpitations, shortness of breath, and nausea.	Treat the cause of the block if it is reversible. Monitor for signs of worsening decreased cardiac output.	Reverse underlying causes. Symptomatic: Medications are prescribed to improve cardiac output until a permanent pacemaker can be placed.	Be aware this type of block can progress to worsening blocks. Seek medical treatment for chest pain, shortness of breath, dizziness, confusion, or fainting.
3rd-Degree AV Block	The impulse from the AV node to the ventricles is blocked. The atria and ventricles beat independently of each other.	Same as 1st-degree block.	There is no correlation between the P and the QRS complex, but the P waves march out consistently and the QRS march out consistently. The QRS complex is the only thing that is able to be measured.	Syncope, chest pain, fatigue, and shortness of breath.	Client may have reduced cardiac output due to poor ventricular filling and slow heart rate. Prepare the client for a pacemaker (temporary or permanent).	Reverse underlying causes. A temporary pacemaker may be initiated until a permanent pacemaker can be placed.	Client will need a pacemaker. Be aware of pre-surgical treatment.

Paced Rhythms

Clients with pacemakers have a set heart rate with unique characteristics on their ECGs referred to as **paced rhythms**. If their heart is atrial paced (A paced), a pacer spike appears before the P wave. If their heart is ventricular paced (V paced), a pacer spike appears before the QRS complex, and the QRS complex will be wide. If their heart is atrial-ventricular (AV) paced, there will

be pacer spikes before the P wave and the QRS complex, and the QRS complex will be wide. See Figure 7.31³⁷ for an image of a ventricular-paced rhythm with pacer spikes appearing before the QRS complex. Characteristics of paced rhythms are summarized in Table 7.4e.



Figure 7.31 Ventricular Paced Rhythm

Table 7.4e Characteristics of Paced Rhythms

Other Rhythms	Pathophysiology	Causes	Identification	Symptoms	Nursing Interventions	Treatment	Patient Education
Paced Rhythms ³⁸	A client who has a pacemaker will have a set rate.	Permanent pacemakers are placed for symptomatic bradycardia, heart blocks, or other dysrhythmias.	<p>If it is atrial paced (A paced), there is a pacer spike before the P wave.</p> <p>If it is ventricular paced (V paced), there is a pacer spike before the QRS complex. The QRS complex will be wide.</p> <p>If it is AV paced, there will be a pacer spike before the P wave and the QRS complex. The QRS complex will be wide.</p>	No symptoms as long as the pacemaker is working appropriately.	Interpret rhythm strip; report inappropriate pacing and pacing abnormalities to the provider.	None.	Take medications as prescribed; call the provider for symptoms such as unexplained edema, shortness of breath, dizziness, hiccups or muscle twitching, or signs of infection around the insertion site. Complete pacer checks as prescribed.

37. "Ventricular Paced Rhythm" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

38. Cleveland Clinic. (2022, February 28). *Permanent pacemaker*. <https://my.clevelandclinic.org/health/symptoms/23213-pulseless-electrical-activity>

ST Segment Abnormality

ST segment abnormality (elevation or depression) indicates myocardial ischemia or myocardial infarction and requires rapid emergency response. Discussion of medical treatment is beyond the scope of this text, but nurses should recognize ST abnormalities on ECGs and seek immediate emergency assistance. See Figure 7.32³⁹ for an image of ST elevation.



Figure 7.32 ST Elevation

39. "Sinus Inferior AMI with ST Elevation.jpg" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

7.5 Cardioversion and Defibrillation

As a nurse becomes familiar with the various types of heart rhythms, it is important to recognize that some rhythms will require immediate intervention and an attempt to restore normal electrical activity within the heart. Without prompt intervention for certain arrhythmias, the client is at risk for cardiac arrest. With any rhythm interpretation, the nurse is responsible for assessing rhythm, identifying the rhythm, and treating the rhythm in collaboration with the medical team.

The purpose of prompt rhythm identification and intervention is to reorganize the electrical conduction within the heart before significant damage can occur. In order to understand how the reorganization of electrical pathways occurs, it is important to recall the normal cardiac conduction pathways. The normal cardiac conduction pathway begins with an electrical impulse from the sinoatrial node (SA) located in the right atrium, to the atrial-ventricle node (AV) located between the atrium and ventricles, down the bundle of His branches located within the ventricular septum, to the Purkinje fibers that deliver the electrical impulses to the ventricular myocardium. As the impulses are transmitted through the ventricular myocardium, they activate the contractions of the right and left ventricles.

When a client is experiencing a serious dysrhythmia, the conduction of the electrical impulse has become altered and the SA node is no longer initiating the rhythm. Cardioversion and defibrillation are used to attempt to reset the heart's normal electrical conduction pathway and put the SA node back in charge.

Cardioversion

Cardioversion involves the use of low-energy electrical shocks to resume the heart's normal electrical rhythm. It is important to remember that cardioversion is only used for dysrhythmia in which the client has a pulse. The typical rhythms that require cardioversion are paroxysmal supraventricular tachycardia (PSVT), supraventricular or narrow complex tachycardia, rapid atrial fibrillation/flutter, torsades de pointes (with a pulse), and ventricular tachycardia (with a pulse). If the client is hemodynamically stable, a provider

may first attempt to convert the rhythm with the use of medications. However, if the client is unstable, immediate cardioversion may be required.

When a client has a heart dysrhythmia but is hemodynamically stable, such as new onset atrial fibrillation or atrial flutter, cardioversion may be a scheduled procedure. In these cases, clients will typically have a transesophageal echocardiogram (TEE) prior to the cardioversion to assess for potential blood clots within the heart, particularly if the rhythm has persisted for greater than 48 hours or the time of rhythm onset is unknown. The TEE procedure involves the use of an ultrasound transducer inserted down into the client's esophagus via endoscope to examine blood flow within the heart. If there is no sign of clot present, the provider can proceed to cardioversion. If a clot is present, the client may require anticoagulation or a different medical treatment to manage the arrhythmia.



As with any invasive medical procedure, the client must complete informed consent prior to proceeding. The nurse ensures that a signed consent is present in the client's medical record and the provider has explained the procedure. The nurse provides patient education about the procedure, including reminding the client they will receive sedation during the procedure, which will limit their memory of the cardioversion.

When preparing the client for cardioversion, electrode patches are placed on the chest in addition to the cardioversion pads. A cardiac monitor is used to monitor the heart rhythm then synchronizes the shock to the existing electrical activity within the client's heart. When the monitor is “synced,” it

identifies the client's R waves and administers the electrical shock during the peak of the R wave. See Figure 7.33¹ for an image of a defibrillator monitor displaying triangles above the R waves of the client's cardiac rhythm, which indicate the monitor has been synced. This synchronization ensures the shock is delivered at the appropriate time in the electrical cycle and minimizes the risk of developing ventricular fibrillation or asystole.



Figure 7.33 Synchronizing the Shock With the R Wave

The majority of cardiac monitors, including automated external defibrillators (AEDs), are biphasic. **Biphasic** monitors deliver current to the client in two directions. In the first phase, current moves from one paddle to the other. In

1. "LIFEPAK_20e_Defibrillator_and_Monitor_displaying_synchronization_with_QRS_complexes_(arrowheads).jpg" by StudentDoctorDG is licensed under [CC BY-SA 4.0](https://creativecommons.org/licenses/by-sa/4.0/)

the second phase, it reverses direction.² The electrical energy levels are determined by the provider and may be as low as 100 to 200 joules. To maintain a safe environment, everyone must remain clear of the client when delivering the electrical shock. No one should touch the client, and the hospital bed and oxygen equipment should be moved away from the client when the shock is delivered. Because the synced cardiac monitor will deliver the electrical shock at the optimal moment of the client's existing cardiac electrical activity, there may be a few second delay from the time the shock is implemented to when it is actually delivered.

Defibrillation

Defibrillation is the immediate administration of an electrical current to help restore normal cardiac function. Defibrillation is administered when the client does not have a pulse. The typical rhythms for defibrillation are ventricular fibrillation, torsades de pointes (without a pulse), and ventricular tachycardia (without a pulse).³ Automated external defibrillators (AEDs) search for these rhythms to determine if a client is experiencing a “shockable rhythm” that may be responsive to an electrical shock.

If a client has a dysrhythmia requiring defibrillation, the nurse must understand that blood is not circulating in the client. Therefore, in addition to the shock, the client requires cardiopulmonary resuscitation (CPR) to circulate blood throughout the body. Because these dysrhythmias are life-threatening and require emergency treatment, informed consent is not obtained. It is imperative for the client to receive the defibrillation shock as rapidly as possible, but high-quality compressions must be administered to maintain perfusion of vital organs until the defibrillator is connected to the client, the rhythm interpreted by the monitor, and shock is advised.

After the defibrillation monitor has arrived near the client, the pads must be placed on the client's chest as quickly as possible to allow the monitor to

2. Li, W., Li, J., Wei, L., Wang, J., Peng, L., Wang, J., Yin, C., & Li, Y. (2021). A framework of current based defibrillation improves defibrillation efficacy of biphasic truncated exponential waveform in rabbits. *Scientific Reports*, 11(1), 1586-1586. <https://doi.org/10.1038/s41598-020-80521-9>

3. Choi, H. J., & Noh, H. (2021). Successful defibrillation using double sequence defibrillation: Case reports. *Medicine*, 100(10), e24992-e24992. <https://doi.org/10.1097/MD.00000000000024992>

analyze the rhythm. During the rhythm analysis process, it is important that no one touches or moves the client. Once the monitor determines if a shock is advised, the staff should continue compressions until the monitor is charged and ready to administer shock at the required joules.

The goal of rapid defibrillation is to stop the disorganized rhythm promptly so the heart's natural pacemaker can hopefully take over with an organized rhythm. Because disorganized rhythms use a tremendous amount of oxygen in already depleted heart tissue, continuing chest compressions for at least two minutes after defibrillation is required to reoxygenate the heart tissue and decrease the risk of the heart going back into ventricular tachycardia or ventricular defibrillation.

Defibrillation does not resolve asystole because an underlying electrical rhythm must be present. During asystole, the heart is in constant polarization and no electrical conduction is occurring.

7.6 Checklist: Initiate Telemetry

**Disclaimer: Always follow agency policy and manufacturer recommendations*

Checklist: Initiate Telemetry^{1,2}

- Verify the provider's order.
- Gather supplies: electrodes.
- Introduce yourself and your role to the client.
- Perform hand hygiene.
- Identify the client using two identifiers and check allergies.
- Provide privacy.
- Explain the procedure to the client regarding the purpose of telemetry, what to expect with lead placement, and telemetry monitoring.
- Prior to applying the electrodes, assess the skin and ensure it is free of excess hair and sweat. Apply the electrodes to clean, dry skin, ensuring good adherence according to manufacturer instructions. The electrodes must make contact with the skin for a clear picture of the heart's electrical activity on the monitor.³ Apply the electrodes to the skin. See Figure 7.34⁴ for an illustration of electrode placement.⁵
 - White – Right arm (RA): Infraclavicular fossa close to the right shoulder
 - Black – Left arm (LA): Infraclavicular fossa close to the left shoulder
 - Red – Left leg (LL): Below the rib cage on the left upper quadrant of

1. *Clinical skills: Essentials collection* (1st ed.). (2021). Elsevier.

2. Lippincott procedures. <http://procedures.lww.com>

3. Drew, B. J., Califf, R. M., Funk, M., Kaufman, E. S., Krucoff, M. W., Laks, M. M., Macfarlane, P. W., Sommargren, C., Swiryn, S., & Van Hare, G. F. (2004). Practice standards for electrocardiographic monitoring in hospital settings. *Circulation*, 110(17), 2721-2746. <https://www.ahajournals.org/doi/10.1161/01.cir.0000145144.56673.59>

4. This image is a derivative of "Patient-monitoring-ECG-lead-configuration-A-5-electrode-lead-configuration-was-used-in.png" by Barbara Drew et al., and is licensed under CC BY 4.0. Access for free at https://www.researchgate.net/publication/267740230_Insights_into_the_Problem_of_Alarm_Fatigue_with_Physiologic_Monitor_Devices_A_Comprehensive_Observational_Study_of_Consecutive_Intensive_Care_Unit_Patients

5. Drew, B. J., Califf, R. M., Funk, M., Kaufman, E. S., Krucoff, M. W., Laks, M. M., Macfarlane, P. W., Sommargren, C., Swiryn, S., & Van Hare, G. F. (2004). Practice standards for electrocardiographic monitoring in hospital settings. *Circulation*, 110(17), 2721-2746. <https://www.ahajournals.org/doi/10.1161/01.cir.0000145144.56673.59>

the abdomen

- Green – Right leg (RL): Below the rib cage on the right upper quadrant of the abdomen
- Brown – (V1): Fourth intercostal space on the right sternal border
- Attach the lead wires to the electrodes.
- Observe the rhythm and print a six-second strip.
- Interpret the rhythm.




Figure 7.34 Electrode Placement for Telemetry



View a YouTube video⁶ showing an instructor demonstration of this skill:



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=320#oembed-1>

6. Chippewa Valley Technical College. (2023, January 5). *Initiating telemetry* [Video]. YouTube. Video licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/). <https://youtu.be/LvE4NrlcuEQ>

7.7 Checklist: Obtain a 12-Lead ECG

**Disclaimer: Always follow agency policy and manufacturer recommendations*

Checklist: Obtain a 12-Lead ECG^{1,2}

- Verify the provider's order.
- Obtain data related to age, gender, cardiac medications, recent blood pressure, and pain level.
- Introduce self and your role.
- Perform hand hygiene.
- Verify the client with two identifiers and check allergies.
- Explain the procedure to the client.
- Provide privacy.
- Enter demographic data as required.
- Remove oil, moisture, and/or excess hair at lead placement points.
- Open the electrode package. Check the expiration date to ensure electrodes are not expired.
- Attach four electrodes to the extremities as indicated on the electrodes.
- Attach the six chest leads in the locations described below.³ View Figure 7.35⁴ for an illustration of ECG lead placement.
 - V1 – Fourth intercostal space on the right sternal border
 - V2 – Fourth intercostal space at the left sternal border
 - V3 – Midway between placement of V2 and V4
 - V4 – Fifth intercostal space at the midclavicular line
 - V5 – Left anterior axillary line on the same horizontal level as V4
 - V6 – Mid-axillary line on the same horizontal level as V4 and V5
- Press the auto button and record the ECG. Ask the client to hold still while

1. *Clinical skills: Essentials collection* (1st ed.). (2021). Elsevier.

2. Lippincott procedures. <http://procedures.lww.com>

3. Drew, B. J., Califf, R. M., Funk, M., Kaufman, E. S., Krucoff, M. W., Laks, M. M., Macfarlane, P. W., Sommargren, C., Swiryn, S., & Van Hare, G. F. (2004). Practice standards for electrocardiographic monitoring in hospital settings. *Circulation*, 110(17), 2721-2746. <https://www.ahajournals.org/doi/10.1161/01.cir.0000145144.56673.59>

4. "Ecg-lead-placement.jpg" by unknown author is used under Fair Use. Access the original at <https://nurseyourownway.com/2016/04/20/demystifying-the-12-lead-ecg/>

the machine is capturing the electrical activity of the heart to ensure a clear and accurate depiction of the heart's electrical pattern.

- Inspect the tracing printout for quality. The ECG machine will provide an interpretation of the electrical activity, but a health care provider will evaluate the findings.
- If the client has an abnormal cardiac pattern, assess their level of consciousness, carotid pulse, and for complaints of chest pain or shortness of breath. Request emergency assistance if indicated.
- Remove the electrodes and clean the skin. Assess the area for redness and irritation.
- Remove gloves and perform hand hygiene.
- Provide for client comfort and safety.
- Notify the health care provider of abnormalities.





Figure 7.35 12-Lead ECG Placement



- RA Right Arm
- LA Left Arm
- LL Left Leg
- RL Right Leg



View a YouTube video⁵ showing an instructor demonstration of this skill:

5. Chippewa Valley Technical College. (2023, January 5). *Obtaining a 12-lead ECG* [Video]. YouTube. Video licensed under CC BY 4.0. <https://youtu.be/Ud6nr-hxA80>



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=322#oembed-1>

Sample Documentation:

11/25/20XX 1030

Obtained a routine 12-lead ECG for a client scheduled for surgery in the morning. Explained the procedure to the client. Performed the 12-lead ECG and assessed the quality of the tracing. Removed the electrodes and no signs of redness or irritation present on skin. The client tolerated the procedure well. ECG results were provided to the health care provider.

Michael Jones, RN

7.8 Checklist: Interpret an ECG

**Disclaimer: Always follow agency policy and manufacturer recommendations*

Checklist: Interpret an ECG

- Accurately calculate the ventricular rate.
- Accurately determine whether the rhythm is regular or irregular.
- Accurately assess the P waves.
- Accurately measure the PR interval.
- Accurately measure the QRS complex.
- Accurately evaluate the T waves.
- Accurately determine the QT interval.
- Accurately evaluate for other components.
- Accurately identify the type of rhythm represented.



View a YouTube video¹ showing an instructor demonstration of this skill:



One or more interactive elements has been excluded from this version of the text. You can view them online here: <https://wtcs.pressbooks.pub/nursingadvancedskills/?p=324#oembed-1>

1. Chippewa Valley Technical College. (2023, January 5). *Interpreting an ECG* [Video]. YouTube. Video licensed under [CC BY 4.0](#). <https://youtu.be/IMSi4LOZ7Yg>

7.9 Spotlight Application

A 65-year-old male client with no past cardiac medical history comes into the Emergency Department complaining of palpitations and shortness of breath. He tells the triage nurse it started about two hours ago. He states he has felt these palpitations before, but they always went away after about ten minutes. The nurse attaches the ECG leads and connects the monitor. The rhythm in Figure 7.36¹ appears on the monitor.




Figure 7.36 Rhythm

Reflection Questions:

1. Interpret this cardiac rhythm.
2. Does this rhythm require emergency assistance?
3. Is this client a candidate for defibrillation or synchronized cardioversion?

Answers:

Here are the steps the nurse took to interpret this rhythm:

1. The nurse calculates the ventricular rate of 120 beats per minute by counting 12 R waves in the 6-second strip (i.e., over 30 large boxes) and multiplies this by 10 to reach 120. The atrial rate cannot be calculated because there are no discernible P waves.
2. The nurse classifies this rhythm as an irregularly irregular rhythm because

1. "Rhythm.jpg" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

the R waves are not equal distances apart.

3. The nurse assesses the P waves. There are no P waves present, so these heartbeats are not originating in the SA node.
4. The PR interval cannot be calculated because there are no P waves.
5. The QRS duration ranges between 0.04 to 0.12 seconds (1 – 3 small boxes).
6. The T waves cannot be evaluated in this lead because the quivering atria (i.e., P waves) obscure them.
7. The ST segment cannot be evaluated in this lead because of the lack of discernible T waves.
8. The QT interval cannot be evaluated in this lead because of the lack of discernible T waves.
9. The quivering waves on the ECG strip between the R waves indicate the atria are quivering, which is a characteristic of atrial fibrillation.
10. The nurse assesses the client for signs and symptoms of decreased cardiac output such as decreased blood pressure, decreased peripheral pulses, prolonged capillary refill, dizziness, chest pain, confusion, and loss of consciousness. The client is stable without signs of decreased cardiac output at this time.

The client is diagnosed by the provider with new onset, stable atrial fibrillation. Because the client presented to the hospital within 48 hours of onset, he is a candidate for a synchronized cardioversion. The nurse anticipates an order for administration of anticoagulant medication and to set up for a cardioversion procedure by the cardiologist.

The Rest of the Story:

Cardioversion is completed, and the client successfully returns to a normal sinus rhythm. He is discharged the next day with a follow-up outpatient appointment with cardiology services to ensure he remains in normal sinus rhythm with prescribed medications.

7.10 Learning Activities



An interactive H5P element has been excluded from this version of the text. You can view it online here:

<https://wtcs.pressbooks.pub/nursingadvancedskills/?p=330#h5p-17>

- ▶ Cardiac Rhythm Flashcard Identification: [Cardiac Rhythm Flashcards](#)

- ▶ Cardiac Rhythm Interpretation Game: [Rhythm Interpretation](#)



Test your knowledge using a NCLEX Next Generation-style ▶ [question](#). You may reset and resubmit your answers to this question an unlimited number of times.

VII Glossary

12-lead electrocardiogram: A diagnostic test (referred to as an ECG or EKG) that uses leads attached to the client's body to record the electrical activity of the heart on special graph paper.

Aorta: A large artery that carries oxygen-rich blood to the rest of the body.

Aortic valve: The valve that opens when blood flows out of the left ventricle to the aorta.

Arrhythmia: Also referred to as a dysrhythmia; a chronic deviation from the normal pattern of impulse conduction and contraction.

Arteries: Vessels that carry oxygen-rich blood from the heart to the body's tissues.

Artifact: Interference with the tracing of the cardiac pattern on an ECG.

Asystole: No cardiac pattern on the ECG and the client does not have a pulse.

Atrial fibrillation (A-fib): An irregular heart rhythm originating in the heart's upper chambers (atria) characterized by atrial quivering, lack of clear P waves, and a wavy baseline on the ECG tracing.

Atrial flutter: A condition where the heart's upper chambers (atria) beat too quickly. This causes the heart to beat in a fast, but usually regular, rhythm and is characterized by a sawtooth pattern on the ECG tracing.

Atrial rhythms: Rhythms that originate in the atria rather than in the SA node.

Atrioventricular (AV) blocks: Conduction blocks that can occur anywhere between the SA node and Purkinje fibers.

Atrioventricular (AV) node: Node located in the lower part of the right atrium, which carries electrical signals from the SA node to the ventricles.

Atrioventricular (AV) valves: The valves located between the atria and ventricles within the heart.

Bigeminy: An abnormal heart rhythm where a premature ventricular contraction (PVC) occurs every other beat.

Biphasic: Two phases.

Bradycardia: Heart rate less than 60 beats per minute.

Bundle branch blocks: Conduction block of either left or right bundle branches and occur within the ventricles.

Bundle of His: A collection of cardiac cells found along the septum between the ventricles that sends electrical impulses from the AV node to the left and right bundle branches.

Capillaries: Small blood vessels where the body exchanges oxygen and carbon dioxide in the blood at the cellular level.

Cardioversion: The use of low-energy shocks to resume the heart's normal electrical rhythm.

Coronary arteries: Blood vessels that run along the heart's surface and carry oxygenated blood to heart tissue.

Couplets: Premature Ventricular Contractions (PVCs) occurring in pairs.

Decreased cardiac output: Lack of blood being pumped out of the heart by the ventricles causing signs and symptoms of decreased blood pressure, decreased pulses, increased capillary refill, dizziness, light-headedness, fainting, chest pain, or shortness of breath.

Defibrillation: The use of an electrical current administered immediately to a patient to help restore normal cardiac function.

Dysrhythmia: Also referred to as an arrhythmia; a chronic deviation from the normal pattern of impulse conduction and contraction.

Electrocardiograms (ECGs): Electrodes are attached to a client's body to record the electrical activity of the heart on special graph paper or on a cardiac monitor.

Endocardium: The inner layer of the heart.

Epicardium: The protective outer layer of the heart.

First-degree AV block: There is a slowed impulse from the AV node to the ventricles.

Heart block: A conduction block that can occur due to any obstruction in the normal pathway of electrical conduction through the heart. The anatomical location of the block can be categorized as in the sinus node, atrioventricular node, or bundle branches.

Inferior vena cava: Carries deoxygenated blood from the lower body.

Isoelectric line: The baseline of the ECG tracing.

Left atrium: The upper left chamber of the heart receives the oxygenated blood and pumps it through the mitral valve into the left ventricle.

Left bundle branch: Offshoots from the bundle of His that send electrical impulses to the left ventricle.

Left ventricle: The lower left chamber of the heart.

Mitral valve: The valve between the left atrium and left ventricle.

Multifocal: Dysrhythmias cause the waveforms to look different because the impulse is originating from different areas of the heart

Myocardial infarction (MI): An emergency medical condition caused by a lack of blood flow to the heart muscle.

Myocardium: The muscular middle layer of the heart.

Normal sinus rhythm (NSR): Originates from the sinus node and describes the characteristic rhythm of the healthy human heart.

Paced rhythms: A client who has a pacemaker with a set heart rate.

P-P interval: The interval that represents the duration between atrial heartbeats.

Pericardium: The protective sac that covers the entire heart.

Premature atrial contractions (PAC): An ectopic beat that originates in the atria.

Premature ventricular contractions (PVCs): A random ventricular contraction stimulated by an area of the heart other than the SA node and characterized by a wide, bizarre QRS complex.

Pulmonary arteries: Arteries that carry deoxygenated blood to the lungs.

Pulmonary valve: The valve that opens when blood flows from the right ventricle into the pulmonary arteries (then to the lungs).

Pulmonary veins: Arteries that carry oxygenated blood back to the left atrium.

Pulseless electrical activity (PEA): There is electrical activity in the heart, but it is not strong enough to cause a contraction or a pulse.

Purkinje fibers: A network of thin filaments that carry electrical impulses that cause the ventricles to contract and pump blood out of the heart.

R-R interval: The interval that represents the duration between the ventricular heartbeats.

R on T phenomenon: When a PVC occurs on the T wave.

Respiratory sinus arrhythmia: Rhythm correlates to the respiratory cycle;

the rate increases when the client breathes in and slows when they breathe out.

Right atrium: Two large veins called the superior vena cava and the inferior vena cava deliver oxygen-poor blood to the upper right chamber of the heart.

Right bundle branch: Offshoots from the bundle of His that send electrical impulses to the right ventricle.

Right ventricle: This lower right chamber of the heart pumps the oxygen-poor blood through the pulmonary valves and then through the pulmonary arteries to the lungs.

Second-degree Type 1 AV block: The impulse from the AV node to the ventricles gets slower and slower with each beat until there is a dropped beat. The pattern then repeats itself.

Second-degree Type 2 AV block: The impulse from the AV node to the ventricles is variable. Some beats will be normal, and other beats will be dropped.

Semilunar (SL) valves: Valves that open when blood flows out of the ventricles.

Sinoatrial blocks: Failed conduction of the impulses beyond the SA node, resulting in prolonged PR intervals or dropped P waves on the ECG

Sinoatrial (SA) node: Node located in the upper part of the right atrium and a major element of the conduction system.

Sinus bradycardia: A sinus rhythm that is a slower rate than normal (i.e., less than 60 beats per minute in an adult).

ST elevation: An elevation of the ST segment on an ECG that can indicate myocardial infarction.

Superior vena cava: Carries deoxygenated blood from the upper body.

Supraventricular tachycardia (SVT): An irregularly fast but regular heart rhythm that affects the heart's upper chambers. SVT is also called paroxysmal supraventricular tachycardia.

Tachycardia: Heart rate greater than 100 bpm.

Telemetry: A portable device used to continuously monitor clients' heart rhythms.

Third-degree AV block: The impulse from the AV node to the ventricles is blocked. The atriums and ventricles beat independently of each other.

Torsades de pointes: A life-threatening ventricular tachycardia that can be caused from long QT intervals or magnesium deficiency.

Tricuspid valve: The valve between the right atrium and right ventricle.

Trigeminy: An abnormal heart rhythm where a premature ventricular contraction (PVC) occurs every third beat.

Unifocal: Dysrhythmias causes the waveforms to look the same because the signal is originating from the same area in the heart

Veins: Carry oxygen-poor blood back to the heart.




Ventricular fibrillation: An abnormal heart rhythm with disorganized electrical conduction signals causing the lower chambers of the heart (ventricles) to twitch (quiver) uselessly and not pump blood to the rest of the body.

Ventricular rhythms: Rhythms that originate in the ventricles (rather than the SA node) and cause the heart to beat faster.

Ventricular tachycardia: An abnormal heart rhythm originating in the lower chambers of the heart (ventricles) characterized by regular, wide QRS complexes, no P waves, and a rate of 150-300 per minute with or without a pulse.

Appendix of Rhythm Strips

Alphabetized List of Selected ECG Patterns

ECG Pattern	Image of Pattern
<p>Figure 7.37 Artifact¹</p>	 <p>Figure 7.37 Artifact</p>
<p>Figure 7.38 Asystole²</p>	 <p>Figure 7.38 Asystole</p>
<p>Figure 7.39 Atrial Fibrillation³</p>	 <p>Figure 7.39 Atrial Fibrillation</p>
<p>Figure 7.40 Atrial Flutter⁴</p>	 <p>Figure 7.40 Atrial Flutter</p>

1. "[Sinus Rhythm with Artifact](#)" by Deanna Hoyord is licensed under [CC BY 4.0](#)
2. "[Asystole](#)" by Deanna Hoyord is licensed under [CC BY 4.0](#)
3. "[Atrial Fibrillation](#)" by Deanna Hoyord is licensed under [CC BY 4.0](#)
4. "[Atrial Flutter](#)" by Deanna Hoyord is licensed under [CC BY 4.0](#)

Figure 7.41 Bradycardia⁵



Figure 7.41
Bradycardia

Figure 7.42 First-Degree Heart Block⁶




Figure 7.42
First-Degree Heart
Block

Figure 7.43 Normal Sinus Rhythm⁷




Figure 7.43 Normal
Sinus Rhythm

Figure 7.44 Premature Ventricular Contraction (PVC) – Unifocal⁸




Figure 7.44 Premature
Ventricular
Contraction (PVC) –
Unifocal

5. "Sinus Bradycardia" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

6. "[1st Degree Heart Block](#)" by Deanna Hoyord is licensed under [CC BY 4.0](#)
7. "[Normal Sinus Rhythm](#)" by Deanna Hoyord is licensed under [CC BY 4.0](#)
8. "[Sinus Rhythm with Unifocal PVCs](#)" by Deanna Hoyord is licensed under [CC BY 4.0](#)

Figure 7.45 Premature Ventricular Contractions (PVCs) – Couplet⁹




Figure 7.45 Premature Ventricular Contractions (PVCs) – Couplets

Figure 7.46 Second-Degree Heart Block Type II¹⁰



Figure 7.46 Second-Degree Heart Block Type II

Figure 7.47 Sinus Tachycardia¹¹




Figure 7.47 Sinus Tachycardia

9. "Bigeminy PVCs" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

10. "2nd Degree Type II AV Block.jpg" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

11. "Sinus Tachycardia.jpg" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

Figure 7.48 ST Elevation¹²



Figure 7.48 ST Elevation

Figure 7.49 Supraventricular Tachycardia (SVT)¹³




Figure 7.49 Supraventricular Tachycardia

Figure 7.50 Third-Degree Heart Block¹⁴



Figure 7.50 Third-Degree Heart Block

Figure 7.51 Torsades de Pointes¹⁵



Figure 7.51 Torsades de Pointes

Figure 7.52 Ventricular Fibrillation¹⁶




Figure 7.52 Ventricular Fibrillation

Figure 7.53 Ventricular Paced Rhythm¹⁷



Figure 7.53 Ventricular Paced Rhythm

Figure 7.54 Ventricular Tachycardia¹⁸




Figure 7.54 Ventricular Tachycardia

12. "Sinus Inferior AMI with ST Elevation.jpg" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

13. "Supraventricular Tachycardia" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

14. "Third Degree Heart Block.jpg" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

15. "Torsades de Pointes" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

16. "Ventricular Fibrillation" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

17. "Ventricular Paced Rhythm" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

18. "Ventricular Tachycardia" by Deanna Hoyord is licensed under [CC BY 4.0](https://creativecommons.org/licenses/by/4.0/)

PART VIII
ANSWER KEYS

Chapter 1

Case Study #1

1. When initiating an IV for Eli, you will consider the following:
 - Client assessment: Check Eli's vital signs, hydration status, and any underlying medical conditions.
 - Site selection: Choose the best IV site, taking into consideration the age of the client, access, and current skin condition.
 - Equipment and supplies: Ensure you have all necessary equipment, such as an IV catheter, tubing, and a sterile dressing. The catheter size for a child will be smaller, and a 22-gauge or 24-gauge catheter may be appropriate.
 - Safety measures: Follow standard infection control procedures to prevent transmission of infectious diseases.
 - Client comfort: Explain the procedure to Eli in age-appropriate terms. Include his grandmother and ensure that they understand the process. Offer comfort measures such as a blanket or a favorite toy to minimize stress and anxiety.
 - Proper technique: Follow the proper technique for inserting an IV catheter and document the insertion site.
 - Monitoring: Monitor Eli for any adverse reactions and make note of any changes in his condition.
 - Medication administration: Administer the diphenhydramine as ordered, following proper medication administration guidelines.

All of the answers to the interactive element are found within the element.

Chapter 2

Case Study #1

1) When initiating an IV for Gary, consider the following:

- Age
- Health history (including hypertension, diabetes, and colon cancer)
- Current symptoms and the need for PIV access to administer and deliver the medication
- Location of a vein for IV access
- Infection control measures and sterile technique for IV insertion

2) Based on the supplied metoprolol of 10 mg/10 mL, each dose of metoprolol for Gary will be 5 mg. To administer this dose, you would need to draw 5 mL of the medication into the syringe.

The rate of administration will depend on the administration method. If it is given as a rapid IV push, you would administer the 5 mL dose over 1-2 minutes and then wait 2 minutes and repeat up to three doses as ordered by the MD.

3) Medication Information

Indication and action of medication:

- Metoprolol is indicated for the treatment of hypertension, angina, and heart failure. It works by blocking the effect of certain hormones (epinephrine and norepinephrine) on the heart and blood vessels, which reduces the heart rate, blood pressure, and workload on the heart.

Onset, peak, and duration of the medication:

- Intravenous (IV) metoprolol has an onset time of approximately 5 minutes, a peak effect within 15 to 30 minutes, and a duration of 3 to 6 hours.

Nursing considerations or special instructions for use:

- Monitoring vital signs: Metoprolol can cause bradycardia and

hypotension, so the client's heart rate, blood pressure, and electrocardiogram should be monitored closely.

Assessments pre-, post-, and during administration:

- Pre-administration: Assess blood pressure and heart rate. Also, assess for any known allergies or adverse reactions to beta-blockers.
- During administration: Monitor blood pressure, heart rate, and respiratory rate. Assess for any signs of adverse reactions, such as chest pain, shortness of breath, or swelling of the legs or ankles.
- Post-administration: Monitor blood pressure and heart rate and assess for any changes in symptoms.

Patient education:

- Explain the purpose and action of metoprolol.
- Inform Gary that the medication will be given as a rapid injection into a vein. He may experience the following common side effects:
 - Decreased heart rate
 - Low blood pressure
 - Dizziness
 - Fatigue
- It is important that Gary communicates immediately to the health care provider if he notes any worsening of symptoms or side effects.

Case Study #2

1) When initiating an IV for Karen, consider the following:

- Assess Karen's veins for IV placement, ensuring that the veins are large enough to accommodate the IV catheter. Note the presence of a client's IV fistula, or location of hemodialysis access site, and take care to restrict IV placement to a non-fistula arm.
- Consider the type and amount of fluids Karen requires, taking into

account her chronic kidney disease and biweekly dialysis.

2) Based upon the supply of medication 16mg/8mL, you will administer 4mL of medication IV push.

The IV push should be administered slowly between 2-5 minutes.

3) Medication Information

Indication and action of medication:

- Ondansetron is indicated for the treatment of nausea and vomiting. It acts by blocking the action of serotonin in the brain and gut, which reduces the stimulation of the vomiting center.

Onset, peak, and duration:

The onset of ondansetron is within 15 minutes, with a peak effect within 30 minutes, and a duration of 4 to 8 hours.

Nursing considerations or special instructions for use:

- Assess for potential allergies or adverse reactions to ondansetron before administering.
- Monitor Karen's vital signs and level of consciousness during and after administration.
- Administer the medication slowly to avoid extravasation, which can cause tissue damage.

Assessments pre-, post-, and during administration:

- Pre-administration: Assess Karen's level of nausea, vomiting, and hydration status.
- During administration: Monitor Karen's vital signs and level of consciousness and check for any adverse reactions or extravasation.
- Post-administration: Assess Karen's level of nausea and vomiting and document any adverse reactions or improvement.

Patient education:

- Explain to Karen the purpose and action of the medication and how it may help with her nausea and vomiting.
- Advise Karen to inform the health care provider if she experiences any adverse reactions, such as difficulty breathing, chest pain, or severe headache.
- Explain the importance of proper hydration and encourage Karen to drink clear fluids to prevent dehydration.

All of the answers to the interactive element are found within the element.

Chapter 3

Case Study #1

1. Indications for a blood transfusion for Helen:

- Anemia (Hgb of 6.5 g/dL)
- Fatigue and exhaustion
- Pale appearance

2) Considerations for starting an IV for the blood transfusion:

- Client assessment: Check Helen's vital signs, hydration status, and any underlying medical conditions.
- Site selection: Choose the best IV site, taking into consideration the age of the client, access, and current skin condition. Consider the size of catheter, optimally a 20-gauge catheter or larger for blood administration.
- Equipment and supplies: Ensure you have all necessary equipment, such as an IV catheter, blood tubing, sterile dressing, and saline.
- Safety measures: Follow standard infection control procedures to prevent transmission of infectious diseases.
- Client comfort: Explain the procedure to Helen.

3) Steps to prepare for the administration of blood for Helen:

- Ensure Helen has signed the consent for blood transfusion
- Verify the correct patient with 2 identifiers, blood type, and cross-match
- Check the compatibility of the blood with the client's blood type and cross-match
- Check for any allergies or sensitivities to components of the blood
- Ensure that the blood is labeled

4) Precautions or nursing considerations:

- Monitor for adverse reactions, such as fever, chills, itching, or hives
- Observe for signs of anaphylaxis

- Check the IV site regularly for any signs of infiltration or infection
- Monitor vital signs and fluid status
- Monitor for signs of fluid volume overload; administer transfusion at an appropriate rate to not overload the client

5) Assessments to be completed prior to the blood transfusion:

- Vital signs
- Lung sounds
- Allergies or sensitivities to components of the blood
- Blood type and cross-match

Assessments to be completed during the blood transfusion:

- Vital signs
- Lung sounds
- Fluid status
- IV site
- Any adverse reactions

6) Blood type O- is compatible with O- and O+ blood types.

7) Steps to ensure safety for the client during blood transfusion:

- Verify the correct client and blood type
- Check the compatibility of the blood with the client
- Check for any allergies or sensitivities to components of the blood
- Monitor vital signs, lung sounds, and fluid status
- Observe for signs of adverse reactions

8) Steps for the procedure of administering the blood transfusion:

- Administer furosemide 20 mg IV as ordered
- Complete checks with a second RN
- Attach the transfusion set to the IV tubing
- Begin the transfusion at a slow rate and monitor vital signs

- Observe the client for adverse reactions and adjust the rate as needed
- Document the transfusion, including the amount and rate of transfusion, any adverse reactions, and any changes in the client's condition
- Administer furosemide 20 mg IV between units
- Administer second unit of PRBCs
- Discontinue the transfusion and remove the IV catheter once the transfusion is complete

All of the answers to the interactive element are found within the element.

Chapter 4

Case Study #1

1. Patient education for Autumn regarding her PICC line:

- Explanation of the PICC line: A peripherally inserted central catheter (PICC) line is a long, thin tube inserted into a vein in the arm and passed through the vein until the tip lies in a larger vein near the heart.
- Importance of hand hygiene.
- Avoidance of heavy lifting and vigorous activities that may put pressure on the PICC line or dislodge it.
- Signs and symptoms of PICC line complications such as redness, swelling, pain, and drainage.
- Promptly reporting any concerns or changes to the health care provider.

2. Maintenance care priorities for a PICC line:

- Monitoring for signs of infection at the insertion site.
- Keeping the PICC line and dressing dry and secure. Monitor length of catheter visible at insertion site and arm circumference.
- Changing the dressing as directed.
- Avoiding tugging or pulling the PICC line.

3. Specific concerns related to Autumn's need for a PICC line:

- Assessing for phlebitis (inflammation of the vein) related to the PICC line.
- Monitoring for complications related to the cellulitis.

4. Purpose of the PICC line: The PICC line is used to provide long-term, continuous access to the bloodstream for administering medications or drawing blood.

5. Frequency of PICC line assessment: The PICC line should be assessed every shift or as directed by the health care provider.

6. Changing the dressing for a PICC line: The dressing should be changed every 48-72 hours or as directed by the health care provider. A sterile dressing

should be used, and aseptic technique should be followed to minimize the risk of infection.

7. Difference between PICC line and a peripheral IV: A peripheral intravenous (IV) line is a short-term solution for administering medications or fluids, whereas a PICC line is a long-term solution. A peripheral IV is inserted into a vein in the hand or arm, whereas a PICC line is inserted into a vein in the arm and passed through a large central vein until the tip lies near the heart.

Difference between PICC line and an implanted port: A port is a device similar to a PICC line that is surgically implanted under the skin and has a small reservoir that can be accessed with a needle. Unlike a PICC line, a port does not need to be reinserted, as the port can remain in place for months or years.

All of the answers to the interactive element are found within the element.

Chapter 5

Case Study #1

1. For client education regarding the NG tube, you can explain the purpose of the tube, which is to provide nutrition to the client when they are unable to eat or drink by mouth. You can also explain how the tube will be inserted, the type of food that will be provided through the tube, and any possible side effects or discomfort that may occur during the procedure.
2. Maintenance care priorities for the NG tube include checking the tube's placement, making sure the tube is secure and not kinked, monitoring the client's vital signs, and checking the amount and appearance of drainage from the tube.
3. Specific concerns related to Caroline's need for an NG tube that should be monitored include infection, tube dislodgement, and blockage. You should also consider the client's age, health status, and any prior experience with NG tubes when preparing for placement.
4. The purpose of the NG tube is to provide nutrition and hydration to the client.
5. An NG tube should be assessed regularly, at least once every shift; prior to any instillation of medication, fluids, or substances into the tube; or as needed based on the client's condition.
6. Cues that indicate a further assessment of the NG tube and the client include changes in the client's vital signs, discomfort or pain, and changes in the amount or appearance of drainage from the tube.
7. The technique used to insert the NG tube is typically the nasal method, which involves passing the tube through the client's nose and down into the stomach.

All of the answers to the interactive element are found within the element.

Chapter 6

1. A client is recovering from a thoracotomy and has a right pleural chest tube to drainage. Highlight or place an “X” next to the best indicators showing the client’s condition is resolving and ready for chest tube removal.

	Indicators
X	Improved respiratory status
	Asymmetrical rise and fall of the chest
	Diminished breath sounds over right lower lobe
X	Decreased chest tube drainage
X	Absence of bubbling in the water seal chamber during expiration
X	Improved chest X-ray findings

2. Managing chest tubes and drainage systems is essential for client safety. Place an “X” next to each nursing action to indicate whether it is likely to be effective in improving the client’s condition being treated with a chest tube or if it is ineffective.

Nursing Action	Effective	Ineffective
Promote oxygenation by encouraging frequent position changes, mobilization, and deep breathing and coughing exercises.	X	
Coil the drainage system tubing and secure it to the edge of the client's bed.	X	
Place the drainage system unit on the client's waist during transport.		X
Immediately apply pressure to the chest tube insertion site and apply a sterile petroleum gauze dressing if the tube dislodges.	X	
Perform routine stripping of the chest tube to prevent blood clots from forming.		X
Assess the amount, color, and consistency of drainage in the drainage tubing and in the collection chamber at regular intervals.	X	

3. B

Case Study # 1

1. For client education regarding the chest tube, the following information can be provided:

- Explain that the purpose of the chest tube is to remove excess air, fluid, or blood that may have accumulated in the pleural cavity (the space between the lung and the chest wall) in order to relieve pressure and improve breathing.
- Discuss the procedure and any potential risks, such as infection, bleeding, and pain.
- Emphasize the importance of keeping the chest tube site clean and avoiding physical activities that may cause trauma to the site.

2. Maintenance care priorities for the chest tube include the following:

- Keeping the chest tube site and surrounding area clean and dry.
- Making sure the chest tube is secured in place and not kinked or obstructed.

- Monitoring the chest tube drainage for any changes (amount, color, consistency).
- Assessing the client's vital signs, lung sounds, and breathing patterns regularly.
- Administering pain medication as prescribed.

3. Specific concerns related to Scott's need for a chest tube that should be monitored or addressed are as follows:

- Pain management, especially around the chest tube site.
- Prevention of infection at the chest tube site.
- Potential complications such as re-accumulation of fluid or air in the pleural cavity, displacement of the chest tube, and injury to surrounding structures.
- Proper functioning of the chest tube and chest tube drainage system.

4. When preparing for placement of the chest tube, the following should be considered:

- Obtaining informed consent from the client or their representative.
- Assess the client's airway, breathing, and circulation (ABCs) to ensure that they are stable.
- Checking for allergies or adverse reactions to medications, including local anesthetics.
- Administering pain control measures, such as local anesthesia, as indicated.
- Properly positioning the client to facilitate chest tube placement and minimize discomfort.
- Making sure the necessary equipment and supplies are readily available, such as sterile gloves, gowns, drapes, chest tube insertion tray, sterile solution, dressing materials, and suture materials.

5. Purpose of chest tube:

- The purpose of a chest tube is to relieve pressure in the chest caused by

fluid or air buildup and to help re-expand collapsed lungs.

- Scott's primary diagnosis is likely a pneumothorax or pleural effusion, based on his history of COPD and smoking, as well as his presentation of increased shortness of breath and left-sided chest pain.

6. The chest tube should be assessed every hour after initial placement and with each client assessment, minimally every four hours or more frequently based on client condition.

7. Further assessment for the chest tube would be indicated further by the following:

- Sudden changes in the amount or color of the drainage from the chest tube.
- Increased pain or discomfort at the chest tube site.
- Signs of infection, such as redness, swelling, or discharge.
- Changes in the client's breathing pattern or oxygen saturation level.

All of the answers to the interactive element are found within the element.

Chapter 7

All of the answers to the interactive element are found within the element.

Appendix A - Master Glossary

A

Air embolism: The presence of air in the vascular system that occurs when air is introduced into the venous system and travels to the right ventricle and/or pulmonary circulation. (Chapter 1.3, Chapter 4.2)

Allogeneic blood products: Blood products donated by other people. (Chapter 3.2)

Ampules: Glass containers in 1 mL to 10 mL sizes that hold a single dose of medication in liquid form. (Chapter 2.3)

Anastomosis: A surgical connection between parts of the intestine. (Chapter 5.2)

Anemia: A hematological condition where there is a lack of healthy red blood cells and/or hemoglobin to carry adequate oxygen to the body's tissues. (Chapter 3.2)

Aorta: A large artery that carries oxygen-rich blood to the rest of the body. (Chapter 7.2)

Aortic valve: The valve that opens when blood flows out of the left ventricle to the aorta. (Chapter 7.2)

Arrhythmia: Also referred to as a dysrhythmia; a chronic deviation from the normal pattern of impulse conduction and contraction. (Chapter 7.2)

Arterial blood sampling: Blood is obtained via venipuncture into an artery. (Chapter 1.2)

Arteries: Vessels that carry oxygen-rich blood from the heart to the body's tissues. (Chapter 7.2)

Artifact: Interference with the tracing of the cardiac pattern on an ECG. (Chapter 7.2)

Aseptic-impregnated catheter hub: A specific device or product that has an aseptic particulate embedded within it to prevent biological contaminants from entering a susceptible host. An example of an aseptic-impregnated device is a chlorhexidine impregnated CVAD dressing. (Chapter 4.3)

Aseptic nontouch technique (ANTT): A global standard used to prevent healthcare-acquired infections. ANTT identifies key parts and key sites throughout the preparation and implementation of the procedure. A key part is any sterile part of equipment used during an aseptic procedure, such as needle hubs and dressings. A key site is the insertion site, nonintact skin, or an access site for medical devices connected to clients. ANTT includes four underlying principles to keep in mind while performing invasive procedures:

- Always perform meticulous hand hygiene.
- Never contaminate key parts.
- Touch nonkey parts with confidence.
- Take appropriate infection control precautions. (Chapter 4.3)

Asystole: No cardiac pattern on the ECG and the client does not have a pulse. (Chapter 7.4)

Atrial fibrillation (A-fib): An irregular heart rhythm originating in the heart's upper chambers (atria) characterized by atrial quivering, lack of clear P waves, and a wavy baseline on the ECG tracing. (Chapter 7.4)

Atrial flutter: A condition where the heart's upper chambers (atria) beat too quickly. This causes the heart to beat in a fast, but usually regular, rhythm and is characterized by a sawtooth pattern on the ECG tracing. (Chapter 7.4)

Atrioventricular (AV) blocks: Conduction blocks that can occur anywhere between the SA node and Purkinje fibers. (Chapter 7.4)

Atrioventricular (AV) node: Node located in the lower part of the right atrium, which carries electrical signals from the SA node to the ventricles. (Chapter 7.2)

Atrioventricular (AV) valves: The valves located between the atria and ventricles within the heart. (Chapter 7.2)

Autologous blood transfusion: A procedure in which blood is removed from the patient and returned to their circulation at a later time, instead of relying on blood donated by others (i.e., allogeneic blood). (Chapter 3.2)

B

Basal infusion: Continuous rate of medication administration, regardless of demand attempts. (Chapter 1.7)

Biphasic: Two phases. (Chapter 7.5)

Blood product: Any therapeutic substance derived from human blood, including whole blood and other blood components for transfusion, as well as plasma-derived medicinal products. (Chapter 3.1)

Blown vein: A ruptured vein that is leaking blood. (Chapter 1.3)

Blunt needles: Needleless access devices. (Chapter 2.3)

Bowel obstruction: A mechanical blockage of intestinal contents by a mass, adhesion, hernia, impacted stool, or other physical blockage such as volvulus (i.e., twisting of the stomach or intestine) or intussusception (i.e., one segment of intestine telescopes inside another). Bowel obstructions block the normal passage of bodily fluids such as salivary, gastric, hepatobiliary, and enteric secretions, causing the fluids to build up, resulting in abdominal distension, pain, and nausea. (Chapter 5.2)

Bradycardia: Heart rate less than 60 beats per minute. (Chapter 7.2)

Breakthrough bolus dose: A dose of opioid or non-opioid medication administered by the nurse for breakthrough pain when a patient is receiving patient-controlled analgesia. (Chapter 1.7)

Bundle of His: A collection of cardiac cells found along the septum between the ventricles that sends electrical impulses from the AV node to the left and right bundle branches. (Chapter 7.2)

C

Capillaries: Small blood vessels where the body exchanges oxygen and carbon dioxide in the blood at the cellular level. (Chapter 7.2)

Capillary blood testing: A blood sample collected from the capillary blood

vessels (i.e., tiny blood vessels located near the surface of the skin). (Chapter 1.2)

Catheter embolism: An embolism that occurs when a small part of the cannula breaks off and flows into the vascular system. (Chapter 1.3)

Catheter-related bloodstream infection (CR-BSI): An infection caused by microorganisms introduced into the bloodstream through the puncture site, the hub, or contaminated IV tubing or IV solution, leading to bacteremia or sepsis. A CR-BSI is a hospital-acquired preventable infection and considered an adverse event. (Chapter 1.3)

Central line-associated bloodstream infection (CLABSI): A laboratory-confirmed bloodstream infection not related to an infection at another site that develops within 48 hours of a central line placement. Most CLABSI cases are preventable with proper aseptic techniques, surveillance, and management strategies. (Chapter 4.2)

Central venous access device (CVAD): A type of vascular access that involves the insertion of a tube into a vein in the neck, chest, or groin and threaded into a central vein (most commonly the internal jugular, subclavian, or femoral) and advanced until the terminal lumen resides within the inferior vena cava, superior vena cava, or right atrium. (Chapter 1.2, Chapter 4.1)

Central venous pressure (CVP): Pressure observed within the central veins as the veins enter the right atrium. Central venous pressure is a good indicator of right heart function and is often monitored during fluid resuscitation. (Chapter 4.2)

Chest tube: A catheter inserted into the pleural space in the chest cavity (also referred to as the thoracic cavity or thorax) to remove air, blood, and/or fluids. (Chapter 6.1)

Chylothorax: A collection of lymph in the pleural space. (Chapter 6.2)

Coronary arteries: Blood vessels that run along the heart's surface and carry oxygenated blood to heart tissue. (Chapter 7.2)

Crepitus: Puffiness or crackling that indicates subcutaneous emphysema, the leakage of air into the subcutaneous tissues surrounding the insertion site. (Chapter 6.3)

D

Decreased cardiac output: Lack of blood being pumped out of the heart by the ventricles causing signs and symptoms of decreased blood pressure, decreased pulses, increased capillary refill, dizziness, light-headedness, fainting, chest pain, or shortness of breath. (Chapter 7.4)

Demand dose: Medication dose given on activation of demand (pressing the demand button). (Chapter 1.7)

Dysfibrinogenemia: A coagulation (clotting) disorder characterized by abnormal fibrinogen. (Chapter 3.2)

Dysrhythmia: Also referred to as an arrhythmia; a chronic deviation from the normal pattern of impulse conduction and contraction. (Chapter 7.2)

E

Empyema: A pyogenic infection (pus) of the pleural space. (Chapter 6.2)

Endocardium: The inner layer of the heart. (Chapter 7.2)

Enteral tubes: Tubes placed in the gastrointestinal tract. (Chapter 5.1)

Epicardium: The protective outer layer of the heart. (Chapter 7.2)

Epidural: Administration of analgesics and anesthetics into the spinal fluid via an epidural catheter for severe pain management associated with surgical procedures or during labor and delivery. (Chapter 1.7)

Extravasation: A condition that occurs when vesicant solution (medication) is administered and inadvertently leaks into surrounding tissue, causing damage to surrounding tissue. It is characterized by the same signs and symptoms as infiltration but also includes burning, stinging, redness, blistering, or necrosis of the tissue. (Chapter 1.3, Chapter 2.2, Chapter 4.2)

F

First-pass effect: The action that occurs when a medication must be first metabolized or broken down prior to entering the blood. (Chapter 2.2)

Fluid resuscitation: Infusing a large volume of fluid through the intravenous venous access to restore hemodynamics and optimize tissue perfusion and, ultimately, tissue oxygen delivery. (Chapter 4.2)

Fluoroscopy: A medical procedure that makes a real-time video of the movements inside a part of the body by passing X-rays through the body over a period of time. (Chapter 4.2)

Flushing: A manual injection of 0.9% sodium chloride to clean the catheter. (Chapter 4.3)

H

Heart block: A conduction block that can occur due to any obstruction in the normal pathway of electrical conduction through the heart. The anatomical location of the block can be categorized as in the sinus node, atrioventricular node, or bundle branches. (Chapter 7.4)

Hemodynamic monitoring: The assessment of a critically ill client's circulatory status and includes measurements of central venous pressure, cardiac output, and blood volume. (Chapter 4.2)

Hemolysis: Red blood cell destruction. (Chapter 3.2)

Hemothorax: A collection of blood in the space between the chest wall and the lung (called the pleural cavity). (Chapter 6.2)

Hydrothorax: Accumulation of serous fluid in the pleural space (Chapter 6.2)

Hypertonic solutions: IV fluids with a higher concentration of dissolved particles than blood. (Chapter 1.2)

Hypofibrinogenemia: A rare, autosomal dominant condition characterized

by bleeding and obstetric problems such as abruption, postpartum hemorrhage, and recurrent pregnancy loss. (Chapter 3.2)

Hypotonic solutions: IV fluids with a lower concentration of dissolved solutes than blood. (Chapter 1.2)

I

Ileus: A nonmechanical decrease or stoppage of the flow of intestinal contents that is often an unavoidable consequence of abdominal or retroperitoneal surgery. (Chapter 5.2)

Inferior vena cava: Carries deoxygenated blood from the lower body. (Chapter 7.2)

Infiltration: A condition that occurs when a nonvesicant solution (IV solution) is inadvertently administered into surrounding tissue. Signs and symptoms include pain, swelling, redness, the skin surrounding the insertion site is cool to touch, there is a change in the quality or flow of IV, the skin is tight around the IV site, IV fluid is leaking from IV site, or there are frequent alarms on the IV pump. (Chapter 1.3)

Intravenous push (IV push): Process of introducing a medication or fluid substance directly into the bloodstream via the venous system. (Chapter 2.2)

Intravenous therapy (IV therapy): Administration of a substance directly into a person's vein. (Chapter 1.2)

Isoelectric line: The baseline of the ECG tracing. (Chapter 7.2)

Isotonic solutions: IV fluids with a similar concentration of dissolved particles as blood. (Chapter 1.2)

IV lock: An IV cannula that has been inserted into a vein and saline locked or clamped. (Chapter 2.2)

L

Left atrium: The upper left chamber of the heart receives the oxygenated blood and pumps it through the mitral valve into the left ventricle. (Chapter 7.2)

Left bundle branch: Offshoots from the bundle of His that send electrical impulses to the left ventricle. (Chapter 7.2)

Left ventricle: The lower left chamber of the heart. (Chapter 7.2)

Loading dose: Ordered amount of medication administered at the time of PCA initiation. (Chapter 1.7)

Locking: The injection of a limited volume of a liquid following the catheter flush, for the period of time when the catheter is not used, to prevent intraluminal clot formation and/or catheter colonization. (Chapter 4.3)

Lockout interval: Time period in which no follow-up demand dose may be administered (even if demand button is activated). (Chapter 1.7)

Lockout maximum: The maximum dose of medication that can be administered within a certain period, commonly prescribed to 1 hour limit. (Chapter 1.7)

M

Microaggregate filter: A second-generation blood filter with a pore size of 20–40 µm that removes 75–90% of white cells, which is used to transfuse packed red cells. (Chapter 3.3)

Midline peripheral catheters: Larger peripheral catheters (i.e., 16-18 gauge) that allow for rapid infusions and blood sampling and can be used for longer duration than traditional peripheral catheters. They are ultrasound-guided and can be inserted by RNs with additional training or other trained professionals. (Chapter 1.2)

Mitral valve: The valve between the left atrium and left ventricle. (Chapter 7.2)

Multifocal: Dysrhythmias cause the waveforms to look different because the impulse is originating from different areas of the heart. (Chapter 7.4)

Myocardial infarction (MI): An emergency medical condition caused by a lack of blood flow to the heart muscle. (Chapter 7.2)

Myocardium: The muscular middle layer of the heart. (Chapter 7.2)

N

Nasogastric (NG) tube: A flexible plastic tube inserted through a nostril, down the posterior oropharynx, and into the stomach or the upper portion of the small intestine. It is typically used for decompression of the stomach for clients with an intestinal obstruction or ileus or for administration of nutrition or medication to clients who are unable to tolerate oral intake. (Chapter 5.2)

Negative pressure: During inspiration (also called inhalation), the diaphragm contracts and pulls downward, while the intercostal muscles between the ribs pull upward. This movement increases the size of the thoracic cavity, thus decreasing the pressure inside. This change in pressure on inspiration is referred to as negative pressure. As a result, a vacuum effect is created and air rushes into the lungs. (Chapter 6.2)

Normal sinus rhythm (NSR): Originates from the sinus node and describes the characteristic rhythm of the healthy human heart. (Chapter 7.4)

P

Patient-controlled analgesia (PCA): A method of pain management that allows hospitalized patients with severe pain to safely self-administer opioid

medications using a programmed pump according to their level of discomfort. (Chapter 1.7)

Pericardium: The protective sac that covers the entire heart. (Chapter 7.2)

Peripheral IV (PIV): A short intravenous catheter inserted by percutaneous venipuncture into a peripheral vein and held in place with a sterile transparent dressing. (Chapter 1.2)

Phlebitis: The inflammation of the vein's inner lining, the tunica intima. Clinical indications are localized redness, pain, heat, and swelling that can track up the vein leading to a palpable venous cord. (Chapter 1.3, Chapter 2.2)

Pleural effusion: Accumulation of fluid in the pleural space, often due to a medical condition such as cancer or heart, kidney, or liver failure. (Chapter 6.2)

Pleural space: Also referred to as the pleural cavity; the space between the membranes of the chest wall (i.e., visceral pleura membrane) and the lung (i.e., the parietal pleura membrane). (Chapter 6.2)

Pneumothorax: A collapsed lung that occurs when air leaks into the space between the lung and chest wall. (Chapter 6.2)

P-P interval: The interval that represents the duration between atrial heartbeats. (Chapter 7.2)

Precipitate: Formation of small crystals as the incompatible substances come into contact with one another. (Chapter 2.2)

Prefilled syringe: Syringes that contain prefilled volumes of medication within the device. (Chapter 2.3)

Premature ventricular contractions (PVCs): A random ventricular contraction stimulated by an area of the heart other than the SA node and characterized by a wide, bizarre QRS complex. (Chapter 7.4)

Pulmonary arteries: Arteries that carry deoxygenated blood to the lungs. (Chapter 7.2)

Pulmonary edema: A condition caused by excess fluid accumulation in the lungs due to excessive fluid in the circulatory system. It is characterized by decreased oxygen saturation; increased respiratory rate; fine or coarse crackles in the lung bases; restlessness; breathlessness; dyspnea; and coughing up pink, frothy sputum. Pulmonary edema requires prompt medical attention and treatment. (Chapter 1.3)

Pulmonary valve: The valve that opens when blood flows from the right ventricle into the pulmonary arteries (then to the lungs). (Chapter 7.2)

Pulmonary veins: Arteries that carry oxygenated blood back to the left atrium. (Chapter 7.2)

Purkinje fibers: A network of thin filaments that carry electrical impulses that cause the ventricles to contract and pump blood out of the heart. (Chapter 7.2)

R

Reservoir pocket: A small pocket, either a plastic or metal cylinder, usually placed just below the collar bone and connected to a catheter that enters a large vein such as the subclavian. (Chapter 4.2)

Right atrium: Two large veins called the superior vena cava and the inferior vena cava deliver oxygen-poor blood to the upper right chamber of the heart. (Chapter 7.2)

Right bundle branch: Offshoots from the bundle of His that send electrical impulses to the right ventricle. (Chapter 7.2)

Right ventricle: This lower right chamber of the heart pumps the oxygen-poor blood through the pulmonary valves and then through the pulmonary arteries to the lungs. (Chapter 7.2)

R on T phenomenon: When a PVC occurs on the T wave. (Chapter 7.4)

R-R interval: The interval that represents the duration between the ventricular heartbeats. (Chapter 7.2)

S

Saline locks: A short extension set that allows intermittent IV access without ongoing infusion. (Chapter 1.2)

Scrub hub: A scrubbing device with an embedded alcohol product such as chlorhexidine with alcohol or 70% alcohol to disinfect catheter hubs or needleless connectors. (Chapter 4.3)

Semilunar (SL) valves: Values that open when blood flows out of the ventricles. (Chapter 7.2)

Sinoatrial blocks: Failed conduction of the impulses beyond the SA node, resulting in prolonged PR intervals or dropped P waves on the ECG. (Chapter 7.4)

Sinoatrial (SA) node: Node located in the upper part of the right atrium and a major element of the conduction system. (Chapter 7.2)

Speed shock: An adverse systemic reaction when a foreign substance is introduced into the bloodstream. (Chapter 2.2)

Spontaneous pneumothorax: Collapse of a lung that occurs suddenly without any known cause. (Chapter 6.2)

ST elevation: An elevation of the ST segment on an ECG that can indicate myocardial infarction. (Chapter 7.2)

Stomach decompression: A medical term that refers to removing stomach contents by using suctioning. Stomach decompression is commonly used after surgery or trauma to reduce pressure from the buildup of fluids and gas that cause pain, nausea, and vomiting and can lead to potential aspiration of stomach contents into the lungs. (Chapter 5.1)

Subcutaneous emphysema: Air leakage into the subcutaneous tissues surrounding the chest tube insertion site. (Chapter 6.3)

Superior vena cava: Carries deoxygenated blood from the upper body. (Chapter 7.2)

Supraventricular tachycardia (SVT): An irregularly fast but regular heart rhythm that affects the heart's upper chambers. SVT is also called paroxysmal supraventricular tachycardia. (Chapter 7.4)

T

Tachycardia: Heart rate greater than 100 bpm. (Chapter 7.2)

Telemetry: A portable device used to continuously monitor clients' heart rhythms. (Chapter 7.2)

Tension pneumothorax: A medical emergency caused by large pneumothorax that affects cardiovascular functioning. (Chapter 6.2)

Thrombocytopenia: Platelet deficiency causing bleeding, bruising, and slow blood clotting after injury. (Chapter 3.2)

Tidaling: When water in the water seal chamber rises with inhalation and falls with exhalation. (Chapter 6.2)

Torsades de pointes: A life-threatening ventricular tachycardia that can be caused from long QT intervals or magnesium deficiency. (Chapter 7.4)

Transfusion reactions: Adverse events that are directly related to the transfusion of blood products and may range from mild to severe with life-threatening effects. Transfusion reactions may be acute or delayed (i.e., up to days or weeks after the transfusion). Immune-related reactions are often due to a mismatch or incompatibility of the transfused blood product and the recipient's blood type or Rh factor. Non-immunologic reactions are typically caused by the physical effects of the blood component or the transmission of a disease. (Chapter 3.2)

Traumatic pneumothorax: Lung collapse caused by a chest injury, such as a bullet wound that pierces the pleural membranes, causing air to rush into the thoracic cavity. (Chapter 6.2)

Tricuspid valve: The valve between the right atrium and right ventricle. (Chapter 7.2)

12-lead electrocardiogram: A diagnostic test (referred to as an ECG or EKG) that uses leads attached to the client's body to record the electrical activity of the heart on special graph paper. (Chapter 7.2)

U

Unifocal: Dysrhythmias causes the waveforms to look the same because the signal is originating from the same area in the heart. (Chapter 7.4)

V

Veins: Blood vessels that typically carry oxygen-deficient blood back to the heart. (Chapter 7.2)

Venipuncture: The process of introducing a needle into a patient's vein to collect a blood sample or insert an IV catheter. (Chapter 1.2)

Ventricular fibrillation: An abnormal heart rhythm with disorganized electrical conduction signals causing the lower chambers of the heart (ventricles) to twitch (quiver) uselessly and not pump blood to the rest of the body. (Chapter 7.4)

Ventricular tachycardia: An abnormal heart rhythm originating in the lower chambers of the heart (ventricles) characterized by regular, wide QRS complexes, no P waves, and a rate of 150-300 per minute with or without a pulse. (Chapter 7.4)

Vesicant medications: Certain medications such as antineoplastic drugs, antibiotics, electrolytes, and vasopressors that can cause severe tissue injury or destruction. (Chapter 4.2)

Vial: A single- or multi-dose plastic container with a rubber seal and covered by a metal or plastic cap. (Chapter 2.3)